Optuna Documentation

Release 3.0.0b0

Optuna Contributors.

CONTENTS:

1	Key Features				
2	Basic Concepts	5			
3 Communication					
4 Contribution 5 License					
					6
7	Indices and tables	319			
Ру	thon Module Index	321			
In	dex	323			



Optuna is an automatic hyperparameter optimization software framework, particularly designed for machine learning. It features an imperative, *define-by-run* style user API. Thanks to our *define-by-run* API, the code written with Optuna enjoys high modularity, and the user of Optuna can dynamically construct the search spaces for the hyperparameters.

CONTENTS: 1

2 CONTENTS:

ONE

KEY FEATURES

Optuna has modern functionalities as follows:

- Lightweight, versatile, and platform agnostic architecture
 - Handle a wide variety of tasks with a simple installation that has few requirements.
- Pythonic search spaces
 - Define search spaces using familiar Python syntax including conditionals and loops.
- Efficient optimization algorithms
 - Adopt state-of-the-art algorithms for sampling hyperparameters and efficiently pruning unpromising trials.
- Easy parallelization
 - Scale studies to tens or hundreds or workers with little or no changes to the code.
- Quick visualization
 - Inspect optimization histories from a variety of plotting functions.

TWO

BASIC CONCEPTS

We use the terms *study* and *trial* as follows:

- Study: optimization based on an objective function
- Trial: a single execution of the objective function

Please refer to sample code below. The goal of a *study* is to find out the optimal set of hyperparameter values (e.g., classifier and svm_c) through multiple *trials* (e.g., n_trials=100). Optuna is a framework designed for the automation and the acceleration of the optimization *studies*.



```
import ...
# Define an objective function to be minimized.
def objective(trial):
    # Invoke suggest methods of a Trial object to generate hyperparameters.
   regressor_name = trial.suggest_categorical('classifier', ['SVR', 'RandomForest'])
   if regressor_name == 'SVR':
        svr_c = trial.suggest_float('svr_c', 1e-10, 1e10, log=True)
       regressor_obj = sklearn.svm.SVR(C=svr_c)
    else:
       rf_max_depth = trial.suggest_int('rf_max_depth', 2, 32)
       regressor_obj = sklearn.ensemble.RandomForestRegressor(max_depth=rf_max_depth)
   X, y = sklearn.datasets.fetch_california_housing(return_X_y=True)
   X_train, X_val, y_train, y_val = sklearn.model_selection.train_test_split(X, y,_
→random state=0)
   regressor_obj.fit(X_train, y_train)
   y_pred = regressor_obj.predict(X_val)
    error = sklearn.metrics.mean_squared_error(y_val, y_pred)
   return error # An objective value linked with the Trial object.
study = optuna.create_study() # Create a new study.
study.optimize(objective, n_trials=100) # Invoke optimization of the objective function.
```

THREE

COMMUNICATION

- GitHub Issues for bug reports, feature requests and questions.
- Gitter for interactive chat with developers.
- Stack Overflow for questions.

CHAPTER	
FOUR	

CONTRIBUTION

Any contributions to Optuna are welcome! When you send a pull request, please follow the contribution guide.

	_
СНАРТЕ	₹
FIVE	Ξ

LICENSE

MIT License (see LICENSE).

12 Chapter 5. License

SIX

REFERENCE

Takuya Akiba, Shotaro Sano, Toshihiko Yanase, Takeru Ohta, and Masanori Koyama. 2019. Optuna: A Next-generation Hyperparameter Optimization Framework. In KDD (arXiv).

6.1 Installation

Optuna supports Python 3.6 or newer.

We recommend to install Optuna via pip:

\$ pip install optuna

You can also install the development version of Optuna from master branch of Git repository:

\$ pip install git+https://github.com/optuna/optuna.git

You can also install Optuna via conda:

\$ conda install -c conda-forge optuna

6.2 Tutorial

If you are new to Optuna or want a general introduction, we highly recommend the below video.

6.2.1 Key Features

Showcases Optuna's Key Features.

1. Lightweight, versatile, and platform agnostic architecture

Optuna is entirely written in Python and has few dependencies. This means that we can quickly move to the real example once you get interested in Optuna.

Quadratic Function Example

Usually, Optuna is used to optimize hyperparameters, but as an example, let's optimize a simple quadratic function: $(x-2)^2$.

First of all, import optuna.

```
import optuna
```

In optuna, conventionally functions to be optimized are named *objective*.

```
def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2
```

This function returns the value of $(x-2)^2$. Our goal is to find the value of x that minimizes the output of the objective function. This is the "optimization." During the optimization, Optuna repeatedly calls and evaluates the objective function with different values of x.

A *Trial* object corresponds to a single execution of the objective function and is internally instantiated upon each invocation of the function.

The suggest APIs (for example, $suggest_float()$) are called inside the objective function to obtain parameters for a trial. $suggest_float()$ selects parameters uniformly within the range provided. In our example, from -10 to 10.

To start the optimization, we create a study object and pass the objective function to method optimize() as follows.

```
study = optuna.create_study()
study.optimize(objective, n_trials=100)
```

You can get the best parameter as follows.

```
best_params = study.best_params
found_x = best_params["x"]
print("Found x: {}, (x - 2)^2: {}".format(found_x, (found_x - 2) ** 2))
```

Out:

```
Found x: 1.9969962048537415, (x - 2)^2: 9.02278528068601e-06
```

We can see that the x value found by Optuna is close to the optimal value of 2.

Note: When used to search for hyperparameters in machine learning, usually the objective function would return the loss or accuracy of the model.

Study Object

Let us clarify the terminology in Optuna as follows:

- **Trial**: A single call of the objective function
- Study: An optimization session, which is a set of trials
- **Parameter**: A variable whose value is to be optimized, such as x in the above example

In Optuna, we use the study object to manage optimization. Method *create_study()* returns a study object. A study object has useful properties for analyzing the optimization outcome.

To get the dictionary of parameter name and parameter values:

```
study.best_params
```

Out:

```
{'x': 1.9969962048537415}
```

To get the best observed value of the objective function:

```
study.best_value
```

Out:

```
9.02278528068601e-06
```

To get the best trial:

```
study.best_trial
```

Out:

```
FrozenTrial(number=54, values=[9.02278528068601e-06], datetime_start=datetime.

datetime(2022, 5, 26, 13, 25, 23, 136962), datetime_complete=datetime.datetime(2022, 5, 26, 13, 25, 23, 140503), params={'x': 1.9969962048537415}, distributions={'x': FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_attrs={}, intermediate_values={}, trial_id=54, state=TrialState.COMPLETE, value=None)
```

To get all trials:

```
study.trials
```

Out:

```
[FrozenTrial(number=0, values=[33.593172646115946], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 22, 963665), datetime_complete=datetime.datetime(2022, 5,
→ 26, 13, 25, 22, 964059), params={'x': 7.795961753334467}, distributions={'x':
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_
→attrs={}, intermediate_values={}, trial_id=0, state=TrialState.COMPLETE, value=None), ___
→FrozenTrial(number=1, values=[19.2398993479497], datetime_start=datetime.datetime(2022,
→ 5, 26, 13, 25, 22, 964566), datetime_complete=datetime.datetime(2022, 5, 26, 13, 25, ...
→22, 964836), params={'x': -2.386330966531105}, distributions={'x':__
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_
→attrs={}, intermediate_values={}, trial_id=1, state=TrialState.COMPLETE, value=None),

FrozenTrial(number=2, values=[58.76075459151562], datetime_start=datetime.

\rightarrow datetime(2022, 5, 26, 13, 25, 22, 965273), datetime_complete=datetime.datetime(2022, 5,
6.2.1 Tantorial ribution (high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_15
→attrs={}, intermediate_values={}, trial_id=2, state=TrialState.COMPLETE, value=None),
→FrozenTrial(number=3, values=[13.673107308468293], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 22, 965964), datetime_complete=datetime.datetime(2022, 5,
```

To get the number of trials:

```
len(study.trials)
```

Out:

100

By executing optimize() again, we can continue the optimization.

```
study.optimize(objective, n_trials=100)
```

To get the updated number of trials:

```
len(study.trials)
```

Out:

200

As the objective function is so easy that the last 100 trials don't improve the result. However, we can check the result again:

```
best_params = study.best_params
found_x = best_params["x"]
print("Found x: {}, (x - 2)^2: {}".format(found_x, (found_x - 2) ** 2))
```

Out:

16

```
Found x: 1.9969962048537415, (x - 2)^2: 9.02278528068601e-06
```

Total running time of the script: (0 minutes 0.800 seconds)

2. Pythonic Search Space

For hyperparameter sampling, Optuna provides the following features:

- optuna.trial.Trial.suggest_categorical() for categorical parameters
- optuna.trial.Trial.suggest_int() for integer parameters
- optuna.trial.Trial.suggest_float() for floating point parameters

With optional arguments of step and log, we can discretize or take the logarithm of integer and floating point parameters.

```
import optuna

def objective(trial):
    # Categorical parameter
    optimizer = trial.suggest_categorical("optimizer", ["MomentumSGD", "Adam"])
```

```
# Integer parameter
num_layers = trial.suggest_int("num_layers", 1, 3)

# Integer parameter (log)
num_channels = trial.suggest_int("num_channels", 32, 512, log=True)

# Integer parameter (discretized)
num_units = trial.suggest_int("num_units", 10, 100, step=5)

# Floating point parameter
dropout_rate = trial.suggest_float("dropout_rate", 0.0, 1.0)

# Floating point parameter (log)
learning_rate = trial.suggest_float("learning_rate", 1e-5, 1e-2, log=True)

# Floating point parameter (discretized)
drop_path_rate = trial.suggest_float("drop_path_rate", 0.0, 1.0, step=0.1)
```

Defining Parameter Spaces

In Optuna, we define search spaces using familiar Python syntax including conditionals and loops.

Also, you can use branches or loops depending on the parameter values.

For more various use, see examples.

• Branches:

```
import sklearn.ensemble
import sklearn.svm

def objective(trial):
    classifier_name = trial.suggest_categorical("classifier", ["SVC", "RandomForest"])
    if classifier_name == "SVC":
        svc_c = trial.suggest_float("svc_c", 1e-10, 1e10, log=True)
        classifier_obj = sklearn.svm.SVC(C=svc_c)
    else:
        rf_max_depth = trial.suggest_int("rf_max_depth", 2, 32, log=True)
        classifier_obj = sklearn.ensemble.RandomForestClassifier(max_depth=rf_max_depth)
```

• Loops:

```
import torch
import torch.nn as nn

def create_model(trial, in_size):
    n_layers = trial.suggest_int("n_layers", 1, 3)
    layers = []
    for i in range(n_layers):
```

(continues on next page)

```
n_units = trial.suggest_int("n_units_1{}".format(i), 4, 128, log=True)
layers.append(nn.Linear(in_size, n_units))
layers.append(nn.ReLU())
in_size = n_units
layers.append(nn.Linear(in_size, 10))
return nn.Sequential(*layers)
```

Note on the Number of Parameters

The difficulty of optimization increases roughly exponentially with regard to the number of parameters. That is, the number of necessary trials increases exponentially when you increase the number of parameters, so it is recommended to not add unimportant parameters.

Total running time of the script: (0 minutes 0.001 seconds)

3. Efficient Optimization Algorithms

Optuna enables efficient hyperparameter optimization by adopting state-of-the-art algorithms for sampling hyperparameters and pruning efficiently unpromising trials.

Sampling Algorithms

Samplers basically continually narrow down the search space using the records of suggested parameter values and evaluated objective values, leading to an optimal search space which giving off parameters leading to better objective values. More detailed explanation of how samplers suggest parameters is in *BaseSampler*.

Optuna provides the following sampling algorithms:

- Grid Search implemented in GridSampler
- Random Search implemented in RandomSampler
- Tree-structured Parzen Estimator algorithm implemented in TPESampler
- CMA-ES based algorithm implemented in CmaEsSampler
- Algorithm to enable partial fixed parameters implemented in PartialFixedSampler
- Nondominated Sorting Genetic Algorithm II implemented in NSGAIISampler
- A Quasi Monte Carlo sampling algorithm implemented in QMCSampler

The default sampler is *TPESampler*.

Switching Samplers

```
import optuna
```

By default, Optuna uses TPESampler as follows.

```
study = optuna.create_study()
print(f"Sampler is {study.sampler.__class__.__name__}")
```

Out:

```
Sampler is TPESampler
```

If you want to use different samplers for example RandomSampler and CmaEsSampler,

```
study = optuna.create_study(sampler=optuna.samplers.RandomSampler())
print(f"Sampler is {study.sampler.__class__.__name__}")
study = optuna.create_study(sampler=optuna.samplers.CmaEsSampler())
print(f"Sampler is {study.sampler.__class__.__name__}")
```

Out:

```
Sampler is RandomSampler
Sampler is CmaEsSampler
```

Pruning Algorithms

Pruners automatically stop unpromising trials at the early stages of the training (a.k.a., automated early-stopping).

Optuna provides the following pruning algorithms:

- Median pruning algorithm implemented in MedianPruner
- Non-pruning algorithm implemented in NopPruner
- Algorithm to operate pruner with tolerance implemented in *PatientPruner*
- Algorithm to prune specified percentile of trials implemented in PercentilePruner
- Asynchronous Successive Halving algorithm implemented in SuccessiveHalvingPruner
- Hyperband algorithm implemented in HyperbandPruner
- Threshold pruning algorithm implemented in *ThresholdPruner*

We use MedianPruner in most examples, though basically it is outperformed by SuccessiveHalvingPruner and HyperbandPruner as in this benchmark result.

Activating Pruners

To turn on the pruning feature, you need to call <code>report()</code> and <code>should_prune()</code> after each step of the iterative training. <code>report()</code> periodically monitors the intermediate objective values. <code>should_prune()</code> decides termination of the trial that does not meet a predefined condition.

We would recommend using integration modules for major machine learning frameworks. Exclusive list is *integration* and usecases are available in ~optuna/examples.

```
import logging
import sys
import sklearn.datasets
import sklearn.linear_model
import sklearn.model_selection
def objective(trial):
    iris = sklearn.datasets.load_iris()
    classes = list(set(iris.target))
   train_x, valid_x, train_y, valid_y = sklearn.model_selection.train_test_split(
        iris.data, iris.target, test_size=0.25, random_state=0
   )
   alpha = trial.suggest_float("alpha", 1e-5, 1e-1, log=True)
   clf = sklearn.linear_model.SGDClassifier(alpha=alpha)
    for step in range(100):
        clf.partial_fit(train_x, train_y, classes=classes)
        # Report intermediate objective value.
        intermediate_value = 1.0 - clf.score(valid_x, valid_y)
        trial.report(intermediate_value, step)
        # Handle pruning based on the intermediate value.
        if trial.should_prune():
            raise optuna.TrialPruned()
   return 1.0 - clf.score(valid_x, valid_y)
```

Set up the median stopping rule as the pruning condition.

```
# Add stream handler of stdout to show the messages
optuna.logging.get_logger("optuna").addHandler(logging.StreamHandler(sys.stdout))
study = optuna.create_study(pruner=optuna.pruners.MedianPruner())
study.optimize(objective, n_trials=20)
```

Out:

```
A new study created in memory with name: no-name-7fe2e6e7-251f-4163-b035-e09e623b5b39

Trial 0 finished with value: 0.07894736842105265 and parameters: {'alpha': 0.

006098101655142042}. Best is trial 0 with value: 0.07894736842105265.

Trial 1 finished with value: 0.052631578947368474 and parameters: {'alpha': 4.

8772293332441534e-05}. Best is trial 1 with value: 0.052631578947368474.
```

```
Trial 2 finished with value: 0.1578947368421053 and parameters: {'alpha': 0.
→0003299485305632669}. Best is trial 1 with value: 0.052631578947368474.
Trial 3 finished with value: 0.23684210526315785 and parameters: {'alpha': 0.
→005022974342604381}. Best is trial 1 with value: 0.052631578947368474.
Trial 4 finished with value: 0.10526315789473684 and parameters: {'alpha': 1.
→0135870821771117e-05}. Best is trial 1 with value: 0.052631578947368474.
Trial 5 pruned.
Trial 6 pruned.
Trial 7 pruned.
Trial 8 finished with value: 0.368421052631579 and parameters: {'alpha': 0.
→0006014029129587075}. Best is trial 1 with value: 0.052631578947368474.
Trial 9 pruned.
Trial 10 pruned.
Trial 11 finished with value: 0.3421052631578947 and parameters: {'alpha': 0.
\rightarrow07286103060376152}. Best is trial 1 with value: 0.052631578947368474.
Trial 12 finished with value: 0.052631578947368474 and parameters: {'alpha': 0.
→005512224515686529}. Best is trial 1 with value: 0.052631578947368474.
Trial 13 pruned.
Trial 14 pruned.
Trial 15 finished with value: 0.2894736842105263 and parameters: {'alpha': 0.
→03850346405841723}. Best is trial 1 with value: 0.052631578947368474.
Trial 16 finished with value: 0.07894736842105265 and parameters: {'alpha': 0.
→0015650464705956582}. Best is trial 1 with value: 0.052631578947368474.
Trial 17 pruned.
Trial 18 pruned.
Trial 19 pruned.
```

As you can see, several trials were pruned (stopped) before they finished all of the iterations. The format of message is "Trial <Trial Number> pruned.".

Which Sampler and Pruner Should be Used?

From the benchmark results which are available at optuna/optuna - wiki "Benchmarks with Kurobako", at least for not deep learning tasks, we would say that

- For RandomSampler, MedianPruner is the best.
- For *TPESampler*, Hyperband is the best.

However, note that the benchmark is not deep learning. For deep learning tasks, consult the below table. This table is from the Ozaki et al., Hyperparameter Optimization Methods: Overview and Characteristics, in IEICE Trans, Vol.J103-D No.9 pp.615-631, 2020 paper, which is written in Japanese.

Parallel Compute Re-	Categorical/Conditional Hyper-	Recommended Algorithms
source	parameters	
Limited	No	TPE. GP-EI if search space is low-dimensional
		and continuous.
	Yes	TPE. GP-EI if search space is low-dimensional
		and continuous
Sufficient	No	CMA-ES, Random Search
	Yes	Random Search or Genetic Algorithm

Integration Modules for Pruning

To implement pruning mechanism in much simpler forms, Optuna provides integration modules for the following libraries.

For the complete list of Optuna's integration modules, see *integration*.

For example, *XGBoostPruningCallback* introduces pruning without directly changing the logic of training iteration. (See also example for the entire script.)

Total running time of the script: (0 minutes 2.037 seconds)

4. Easy Parallelization

It's straightforward to parallelize optuna.study.Study.optimize().

If you want to manually execute Optuna optimization:

- 1. start an RDB server (this example uses MySQL)
- 2. create a study with -storage argument
- 3. share the study among multiple nodes and processes

Of course, you can use Kubernetes as in the kubernetes examples.

To just see how parallel optimization works in Optuna, check the below video.

Create a Study

You can create a study using optuna create-study command. Alternatively, in Python script you can use optuna. create_study().

Then, write an optimization script. Let's assume that foo.py contains the following code.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

if __name__ == "__main__":
    study = optuna.load_study(
        study_name="distributed-example", storage="mysql://root@localhost/example"
```

```
)
study.optimize(objective, n_trials=100)
```

Share the Study among Multiple Nodes and Processes

Finally, run the shared study from multiple processes. For example, run Process 1 in a terminal, and do Process 2 in another one. They get parameter suggestions based on shared trials' history.

Process 1:

Process 2 (the same command as process 1):

Note: n_trials is the number of trials each process will run, not the total number of trials across all processes. For example, the script given above runs 100 trials for each process, 100 trials * 2 processes = 200 trials. *optuna.study. MaxTrialsCallback* can ensure how many times trials will be performed across all processes.

Note: We do not recommend SQLite for distributed optimizations at scale because it may cause deadlocks and serious performance issues. Please consider to use another database engine like PostgreSQL or MySQL.

Note: Please avoid putting the SQLite database on NFS when running distributed optimizations. See also: https://www.sqlite.org/faq.html#q5

Total running time of the script: (0 minutes 0.000 seconds)

5. Quick Visualization for Hyperparameter Optimization Analysis

Optuna provides various visualization features in optuna. visualization to analyze optimization results visually.

This tutorial walks you through this module by visualizing the history of lightgbm model for breast cancer dataset.

For visualizing multi-objective optimization (i.e., the usage of optuna.visualization.plot_pareto_front()), please refer to the tutorial of *Multi-objective Optimization with Optuna*.

```
import lightgbm as lgb
import numpy as np
import sklearn.datasets
import sklearn.metrics
from sklearn.model_selection import train_test_split
import optuna
# You can use Matplotlib instead of Plotly for visualization by simply replacing `optuna.
→visualization` with
# `optuna.visualization.matplotlib` in the following examples.
from optuna.visualization import plot_contour
from optuna.visualization import plot_edf
from optuna.visualization import plot_intermediate_values
from optuna.visualization import plot_optimization_history
from optuna.visualization import plot_parallel_coordinate
from optuna.visualization import plot_param_importances
from optuna.visualization import plot_slice
SEED = 42
np.random.seed(SEED)
```

Define the objective function.

```
def objective(trial):
   data, target = sklearn.datasets.load_breast_cancer(return_X_y=True)
   train_x, valid_x, train_y, valid_y = train_test_split(data, target, test_size=0.25)
   dtrain = lgb.Dataset(train_x, label=train_y)
   dvalid = lgb.Dataset(valid_x, label=valid_y)
   param = {
        "objective": "binary",
        "metric": "auc".
        "verbosity": -1,
        "boosting_type": "gbdt",
        "bagging_fraction": trial.suggest_float("bagging_fraction", 0.4, 1.0),
        "bagging_freq": trial.suggest_int("bagging_freq", 1, 7),
        "min_child_samples": trial.suggest_int("min_child_samples", 5, 100),
   }
   # Add a callback for pruning.
   pruning_callback = optuna.integration.LightGBMPruningCallback(trial, "auc")
   gbm = lgb.train(
       param, dtrain, valid_sets=[dvalid], verbose_eval=False, callbacks=[pruning_

→callback]
```

```
preds = gbm.predict(valid_x)
pred_labels = np.rint(preds)
accuracy = sklearn.metrics.accuracy_score(valid_y, pred_labels)
return accuracy
```

```
study = optuna.create_study(
    direction="maximize",
    sampler=optuna.samplers.TPESampler(seed=SEED),
    pruner=optuna.pruners.MedianPruner(n_warmup_steps=10),
)
study.optimize(objective, n_trials=100, timeout=600)
```

Out:

```
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/

→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/

→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of __
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
```

(continues on next page)

```
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of __
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of ...
LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument insteadhinues on next page)
```

Plot functions

Visualize the optimization history. See *plot_optimization_history()* for the details.

```
plot_optimization_history(study)
```

Visualize the learning curves of the trials. See plot_intermediate_values() for the details.

```
plot_intermediate_values(study)
```

Visualize high-dimensional parameter relationships. See plot_parallel_coordinate() for the details.

```
plot_parallel_coordinate(study)
```

Select parameters to visualize.

```
plot_parallel_coordinate(study, params=["bagging_freq", "bagging_fraction"])
```

Visualize hyperparameter relationships. See *plot_contour()* for the details.

```
plot_contour(study)
```

Select parameters to visualize.

```
plot_contour(study, params=["bagging_freq", "bagging_fraction"])
```

Visualize individual hyperparameters as slice plot. See *plot_slice()* for the details.

```
plot_slice(study)
```

Select parameters to visualize.

```
plot_slice(study, params=["bagging_freq", "bagging_fraction"])
```

Visualize parameter importances. See *plot_param_importances()* for the details.

```
plot_param_importances(study)
```

Learn which hyperparameters are affecting the trial duration with hyperparameter importance.

```
optuna.visualization.plot_param_importances(
    study, target=lambda t: t.duration.total_seconds(), target_name="duration"
)
```

Visualize empirical distribution function. See *plot_edf()* for the details.

```
plot_edf(study)
```

Total running time of the script: (0 minutes 4.495 seconds)

6.2.2 Recipes

Showcases the recipes that might help you using Optuna with comfort.

Saving/Resuming Study with RDB Backend

An RDB backend enables persistent experiments (i.e., to save and resume a study) as well as access to history of studies. In addition, we can run multi-node optimization tasks with this feature, which is described in 4. Easy Parallelization.

In this section, let's try simple examples running on a local environment with SQLite DB.

Note: You can also utilize other RDB backends, e.g., PostgreSQL or MySQL, by setting the storage argument to the DB's URL. Please refer to SQLAlchemy's document for how to set up the URL.

New Study

We can create a persistent study by calling *create_study()* function as follows. An SQLite file example.db is automatically initialized with a new study record.

```
import logging
import sys

import optuna

# Add stream handler of stdout to show the messages
optuna.logging.get_logger("optuna").addHandler(logging.StreamHandler(sys.stdout))
study_name = "example-study" # Unique identifier of the study.
storage_name = "sqlite:///{}.db".format(study_name)
study = optuna.create_study(study_name=study_name, storage=storage_name)
```

Out:

```
A new study created in RDB with name: example-study
```

To run a study, call <code>optimize()</code> method passing an objective function.

```
def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

study.optimize(objective, n_trials=3)
```

Out:

```
Trial 0 finished with value: 1.1553565687859988 and parameters: {'x': 0.9251248589784957}

→. Best is trial 0 with value: 1.1553565687859988.

Trial 1 finished with value: 124.83177267406961 and parameters: {'x': -9.172813999797437}

→. Best is trial 0 with value: 1.1553565687859988.

Trial 2 finished with value: 17.032250701813034 and parameters: {'x': 6.127014744559684}.

→ Best is trial 0 with value: 1.1553565687859988.
```

Resume Study

To resume a study, instantiate a *Study* object passing the study name example-study and the DB URL sqlite://example-study.db.

Out:

```
Using an existing study with name 'example-study' instead of creating a new one.

Trial 3 finished with value: 0.12668907159724158 and parameters: {'x': 2.

3559340832194096}. Best is trial 3 with value: 0.12668907159724158.

Trial 4 finished with value: 19.039682573368243 and parameters: {'x': 6.363448472638154}.

Best is trial 3 with value: 0.12668907159724158.

Trial 5 finished with value: 78.49896784810656 and parameters: {'x': -6.859964325442092}.

Best is trial 3 with value: 0.12668907159724158.
```

Experimental History

We can access histories of studies and trials via the *Study* class. For example, we can get all trials of example-study as:

Out:

```
Using an existing study with name 'example-study' instead of creating a new one.
```

The method trials_dataframe() returns a pandas dataframe like:

```
print(df)
```

Out:

```
number
               value params_x
                                  state
            1.155357 0.925125 COMPLETE
0
1
       1 124.831773 -9.172814 COMPLETE
2
          17.032251 6.127015 COMPLETE
3
           0.126689 2.355934 COMPLETE
4
           19.039683 6.363448 COMPLETE
       4
5
           78.498968 -6.859964 COMPLETE
```

A Study object also provides properties such as trials, best_value, best_params (see also 1. Lightweight, versatile, and platform agnostic architecture).

```
print("Best params: ", study.best_params)
print("Best value: ", study.best_value)
print("Best Trial: ", study.best_trial)
print("Trials: ", study.trials)
```

Out:

```
Best params: {'x': 2.3559340832194096}
Best value: 0.12668907159724158
Best Trial: FrozenTrial(number=3, values=[0.12668907159724158], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 31, 222305), datetime_complete=datetime.datetime(2022, 5,
→ 26, 13, 25, 31, 241490), params={'x': 2.3559340832194096}, distributions={'x': __
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_
→attrs={}, intermediate_values={}, trial_id=4, state=TrialState.COMPLETE, value=None)
Trials: [FrozenTrial(number=0, values=[1.1553565687859988], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 31, 43806), datetime_complete=datetime.datetime(2022, 5, ___
→26, 13, 25, 31, 65252), params={'x': 0.9251248589784957}, distributions={'x': __
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_
→attrs={}, intermediate_values={}, trial_id=1, state=TrialState.COMPLETE, value=None),
→FrozenTrial(number=1, values=[124.83177267406961], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 31, 97591), datetime_complete=datetime.datetime(2022, 5, __
→26, 13, 25, 31, 114237), params={'x': -9.172813999797437}, distributions={'x': __
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_

→attrs={}, intermediate_values={}, trial_id=2, state=TrialState.COMPLETE, value=None),

→FrozenTrial(number=2, values=[17.032250701813034], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 31, 138133), datetime_complete=datetime.datetime(2022, 5,
→ 26, 13, 25, 31, 154230), params={'x': 6.127014744559684}, distributions={'x': ...
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_
→attrs={}, intermediate_values={}, trial_id=3, state=TrialState.COMPLETE, value=None),
→FrozenTrial(number=3, values=[0.12668907159724158], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 31, 222305), datetime_complete=datetime.datetime(2022, 5,
→ 26, 13, 25, 31, 241490), params={'x': 2.3559340832194096}, distributions={'x': ...
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_
→attrs={}, intermediate_values={}, trial_id=4, state=TrialState.COMPLETE, value=None),
→FrozenTrial(number=4, values=[19.039682573368243], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 31, 269243), datetime_complete=datetime.datetime(2022, 5,
→ 26, 13, 25, 31, 287217), params={'x': 6.363448472638154}, distributions={'x': □
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_
→attrs={}, intermediate_values={}, trial_id=5, state=TrialState.COMPLETE, value=None),
→FrozenTrial(number=5, values=[78.49896784810656], datetime_start=datetime.
→datetime(2022, 5, 26, 13, 25, 31, 310321), datetime_complete=datetime.datetime(2022, 5,
\rightarrow 26, 13, 25, 31, 325601), params={'x': -6.859964325442092}, distributions={'x':__
→FloatDistribution(high=10.0, log=False, low=-10.0, step=None)}, user_attrs={}, system_
→attrs={}, intermediate_values={}, trial_id=6, state=TrialState.COMPLETE, value=None)]
```

Total running time of the script: (0 minutes 0.586 seconds)

Multi-objective Optimization with Optuna

This tutorial showcases Optuna's multi-objective optimization feature by optimizing the validation accuracy of Fashion MNIST dataset and the FLOPS of the model implemented in PyTorch.

We use thop to measure FLOPS.

```
import thop
import torch
import torch.nn as nn
import torch.nn.functional as F
```

```
import torchvision
import optuna
DEVICE = torch.device("cuda") if torch.cuda.is_available() else torch.device("cpu")
DIR = ".."
BATCHSIZE = 128
N_TRAIN_EXAMPLES = BATCHSIZE * 30
N_VALID_EXAMPLES = BATCHSIZE * 10
def define_model(trial):
   n_layers = trial.suggest_int("n_layers", 1, 3)
   layers = []
   in_features = 28 * 28
    for i in range(n_layers):
        out_features = trial.suggest_int("n_units_1{}".format(i), 4, 128)
        layers.append(nn.Linear(in_features, out_features))
        layers.append(nn.ReLU())
        p = trial.suggest_float("dropout_{}".format(i), 0.2, 0.5)
        layers.append(nn.Dropout(p))
        in_features = out_features
   layers.append(nn.Linear(in_features, 10))
   layers.append(nn.LogSoftmax(dim=1))
   return nn.Sequential(*layers)
# Defines training and evaluation.
def train_model(model, optimizer, train_loader):
   model.train()
    for batch_idx, (data, target) in enumerate(train_loader):
        data, target = data.view(-1, 28 * 28).to(DEVICE), target.to(DEVICE)
        optimizer.zero_grad()
        F.nll_loss(model(data), target).backward()
        optimizer.step()
def eval_model(model, valid_loader):
   model.eval()
   correct = 0
   with torch.no_grad():
        for batch_idx, (data, target) in enumerate(valid_loader):
            data, target = data.view(-1, 28 * 28).to(DEVICE), target.to(DEVICE)
            pred = model(data).argmax(dim=1, keepdim=True)
            correct += pred.eq(target.view_as(pred)).sum().item()
    accuracy = correct / N_VALID_EXAMPLES
```

(continues on next page)

Define multi-objective objective function. Objectives are FLOPS and accuracy.

```
def objective(trial):
   train_dataset = torchvision.datasets.FashionMNIST(
       DIR, train=True, download=True, transform=torchvision.transforms.ToTensor()
   train_loader = torch.utils.data.DataLoader(
        torch.utils.data.Subset(train_dataset, list(range(N_TRAIN_EXAMPLES))),
       batch_size=BATCHSIZE,
        shuffle=True,
   )
   val_dataset = torchvision.datasets.FashionMNIST(
       DIR, train=False, transform=torchvision.transforms.ToTensor()
   val_loader = torch.utils.data.DataLoader(
        torch.utils.data.Subset(val_dataset, list(range(N_VALID_EXAMPLES))),
        batch_size=BATCHSIZE.
        shuffle=True,
   model = define_model(trial).to(DEVICE)
   optimizer = torch.optim.Adam(
       model.parameters(), trial.suggest_float("lr", 1e-5, 1e-1, log=True)
   )
   for epoch in range(10):
        train_model(model, optimizer, train_loader)
    flops, accuracy = eval_model(model, val_loader)
   return flops, accuracy
```

Run multi-objective optimization

If your optimization problem is multi-objective, Optuna assumes that you will specify the optimization direction for each objective. Specifically, in this example, we want to minimize the FLOPS (we want a faster model) and maximize the accuracy. So we set directions to ["minimize", "maximize"].

```
study = optuna.create_study(directions=["minimize", "maximize"])
study.optimize(objective, n_trials=30, timeout=300)
print("Number of finished trials: ", len(study.trials))
```

Out:

```
Downloading http://fashion-mnist.s3-website.eu-central-1.amazonaws.com/train-images-idx3-_{\hookrightarrow} ubyte.gz
```

```
Downloading http://fashion-mnist.s3-website.eu-central-1.amazonaws.com/train-images-idx3-
→ubyte.gz to ../FashionMNIST/raw/train-images-idx3-ubyte.gz
  0%|
               | 0/26421880 [00:00<?, ?it/s]
  0%|
               | 41984/26421880 [00:00<01:21, 322665.37it/s]
  0%|
               | 104448/26421880 [00:00<01:14, 354936.06it/s]
  1%|
               | 260096/26421880 [00:00<00:33, 782282.75it/s]
  2% | 2
               | 535552/26421880 [00:00<00:17, 1446761.94it/s]
  4% | 4
              | 1067008/26421880 [00:00<00:09, 2703444.26it/s]
  8%|7
              | 2049024/26421880 [00:00<00:04, 4959551.83it/s]
 14%|#4
              | 3728384/26421880 [00:00<00:02, 8648340.29it/s]
 20%|##
              | 5358592/26421880 [00:00<00:01, 11006303.79it/s]
              | 6947840/26421880 [00:00<00:01, 12499498.44it/s]
 26%|##6
              | 8574976/26421880 [00:01<00:01, 13644372.25it/s]
 32%|###2
               | 10223616/26421880 [00:01<00:01, 14504526.84it/s]
 39%|###8
              | 11806720/26421880 [00:01<00:00, 14904558.51it/s]
45%|####4
 51%|#####
              | 13395968/26421880 [00:01<00:00, 15201842.43it/s]
 57%|#####7
              | 15091712/26421880 [00:01<00:00, 15730104.55it/s]
 63%|######3 | 16750592/26421880 [00:01<00:00, 15988081.83it/s]
 70%|#####9 | 18410496/26421880 [00:01<00:00, 16171610.19it/s]
 76%|######6 | 20130816/26421880 [00:01<00:00, 16481352.65it/s]
 83%|######## | 21814272/26421880 [00:01<00:00, 16587301.00it/s]
 89%|####### | 23486464/26421880 [00:01<00:00, 16627604.59it/s]
95%|#######5| 25150464/26421880 [00:02<00:00, 16612180.79it/s]
26422272it [00:02, 12034557.75it/s]
Extracting .../FashionMNIST/raw/train-images-idx3-ubyte.gz to .../FashionMNIST/raw
Downloading http://fashion-mnist.s3-website.eu-central-1.amazonaws.com/train-labels-idx1-
→ubyte.gz
Downloading http://fashion-mnist.s3-website.eu-central-1.amazonaws.com/train-labels-idx1-
→ubyte.gz to ../FashionMNIST/raw/train-labels-idx1-ubyte.gz
  0%|
               | 0/29515 [00:00<?, ?it/s]
29696it [00:00, 298948.14it/s]
Extracting ../FashionMNIST/raw/train-labels-idx1-ubyte.gz to ../FashionMNIST/raw
Downloading http://fashion-mnist.s3-website.eu-central-1.amazonaws.com/t10k-images-idx3-
ubyte.qz
Downloading http://fashion-mnist.s3-website.eu-central-1.amazonaws.com/t10k-images-idx3-
→ubyte.gz to ../FashionMNIST/raw/t10k-images-idx3-ubyte.gz
  0%|
               | 0/4422102 [00:00<?, ?it/s]
              | 40960/4422102 [00:00<00:13, 320163.35it/s]
  1%|
  2% | 2
               | 104448/4422102 [00:00<00:12, 354489.21it/s]
               | 284672/4422102 [00:00<00:04, 867888.24it/s]
  6%16
 13%|#2
              | 568320/4422102 [00:00<00:02, 1529836.75it/s]
              | 1120256/4422102 [00:00<00:01, 2824376.49it/s]
25%|##5
              | 2134016/4422102 [00:00<00:00, 5140600.15it/s]
48%|####8
87%|#######6 | 3825664/4422102 [00:00<00:00, 8808855.70it/s]
4422656it [00:00, 5519398.34it/s]
Extracting ../FashionMNIST/raw/t10k-images-idx3-ubyte.gz to ../FashionMNIST/raw
```

(continues on next page)

Check trials on Pareto front visually.

```
optuna.visualization.plot_pareto_front(study, target_names=["FLOPS", "accuracy"])
```

Out:

Fetch the list of trials on the Pareto front with best_trials.

For example, the following code shows the number of trials on the Pareto front and picks the trial with the highest accuracy.

```
print(f"Number of trials on the Pareto front: {len(study.best_trials)}")

trial_with_highest_accuracy = max(study.best_trials, key=lambda t: t.values[1])
print(f"Trial with highest accuracy: ")
print(f"\tnumber: {trial_with_highest_accuracy.number}")
print(f"\tparams: {trial_with_highest_accuracy.params}")
print(f"\tvalues: {trial_with_highest_accuracy.values}")
```

Out:

Learn which hyperparameters are affecting the flops most with hyperparameter importance.

```
optuna.visualization.plot_param_importances(
    study, target=lambda t: t.values[0], target_name="flops"
)
```

Total running time of the script: (1 minutes 52.901 seconds)

User Attributes

This feature is to annotate experiments with user-defined attributes.

Adding User Attributes to Studies

A *Study* object provides *set_user_attr()* method to register a pair of key and value as an user-defined attribute. A key is supposed to be a str, and a value be any object serializable with json.dumps.

```
import sklearn.datasets
import sklearn.model_selection
import sklearn.svm

import optuna

study = optuna.create_study(storage="sqlite://example.db")
study.set_user_attr("contributors", ["Akiba", "Sano"])
study.set_user_attr("dataset", "MNIST")
```

We can access annotated attributes with user_attr property.

```
study.user_attrs # {'contributors': ['Akiba', 'Sano'], 'dataset': 'MNIST'}
```

Out:

```
{'contributors': ['Akiba', 'Sano'], 'dataset': 'MNIST'}
```

StudySummary object, which can be retrieved by get_all_study_summaries(), also contains user-defined attributes.

```
study_summaries = optuna.get_all_study_summaries("sqlite:///example.db")
study_summaries[0].user_attrs # {"contributors": ["Akiba", "Sano"], "dataset": "MNIST"}
```

Out:

```
{'contributors': ['Akiba', 'Sano'], 'dataset': 'MNIST'}
```

See also:

optuna study set-user-attr command, which sets an attribute via command line interface.

Adding User Attributes to Trials

As with Study, a Trial object provides set_user_attr() method. Attributes are set inside an objective function.

```
def objective(trial):
    iris = sklearn.datasets.load_iris()
    x, y = iris.data, iris.target

    svc_c = trial.suggest_float("svc_c", 1e-10, 1e10, log=True)
    clf = sklearn.svm.SVC(C=svc_c)
    accuracy = sklearn.model_selection.cross_val_score(clf, x, y).mean()
```

(continues on next page)

```
trial.set_user_attr("accuracy", accuracy)

return 1.0 - accuracy # return error for minimization

study.optimize(objective, n_trials=1)
```

We can access annotated attributes as:

```
study.trials[0].user_attrs
```

Out:

```
{'accuracy': 0.94000000000001}
```

Note that, in this example, the attribute is not annotated to a *Study* but a single *Trial*.

Total running time of the script: (0 minutes 0.254 seconds)

Command-Line Interface

Command	Description
ask	Create a new trial and suggest parameters.
best-trial	Show the best trial.
best-trials	Show a list of trials located at the Pareto front.
create-study	Create a new study.
delete-study	Delete a specified study.
storage upgrade	Upgrade the schema of a storage.
studies	Show a list of studies.
study optimize	Start optimization of a study.
study set-user-attr	Set a user attribute to a study.
tell	Finish a trial, which was created by the ask command.
trials	Show a list of trials.

Optuna provides command-line interface as shown in the above table.

Let us assume you are not in IPython shell and writing Python script files instead. It is totally fine to write scripts like the following:

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

if __name__ == "__main__":
    study = optuna.create_study()
    study.optimize(objective, n_trials=100)
    print("Best value: {} (params: {})\n".format(study.best_value, study.best_params))
```

Out:

```
Best value: 0.00011620862415280119 (params: {'x': 1.9892199896033074})
```

However, we can reduce boilerplate codes by using our optuna command. Let us assume that foo.py contains only the following code.

```
def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2
```

Even so, we can invoke the optimization as follows. (Don't care about --storage sqlite:///example.db for now, which is described in Saving/Resuming Study with RDB Backend.)

Please note that foo.py only contains the definition of the objective function. By giving the script file name and the method name of objective function to optuna study optimize command, we can invoke the optimization.

Total running time of the script: (0 minutes 0.363 seconds)

User-Defined Sampler

Thanks to user-defined samplers, you can:

- experiment your own sampling algorithms,
- implement task-specific algorithms to refine the optimization performance, or
- wrap other optimization libraries to integrate them into Optuna pipelines (e.g., *SkoptSampler*).

This section describes the internal behavior of sampler classes and shows an example of implementing a user-defined sampler.

Overview of Sampler

A sampler has the responsibility to determine the parameter values to be evaluated in a trial. When a *suggest* API (e.g., *suggest_float()*) is called inside an objective function, the corresponding distribution object (e.g., *FloatDistribution*) is created internally. A sampler samples a parameter value from the distribution. The sampled value is returned to the caller of the *suggest* API and evaluated in the objective function.

To create a new sampler, you need to define a class that inherits <code>BaseSampler</code>. The base class has three abstract methods; <code>infer_relative_search_space()</code>, <code>sample_relative()</code>, and <code>sample_independent()</code>.

As the method names imply, Optuna supports two types of sampling: one is **relative sampling** that can consider the correlation of the parameters in a trial, and the other is **independent sampling** that samples each parameter independently.

At the beginning of a trial, <code>infer_relative_search_space()</code> is called to provide the relative search space for the trial. Then, <code>sample_relative()</code> is invoked to sample relative parameters from the search space. During the execution of the objective function, <code>sample_independent()</code> is used to sample parameters that don't belong to the relative search space.

Note: Please refer to the document of *BaseSampler* for further details.

An Example: Implementing SimulatedAnnealingSampler

For example, the following code defines a sampler based on Simulated Annealing (SA):

```
import numpy as np
import optuna
class SimulatedAnnealingSampler(optuna.samplers.BaseSampler):
   def __init__(self, temperature=100):
        self._rng = np.random.RandomState()
        self._temperature = temperature # Current temperature.
        self._current_trial = None # Current state.
    def sample_relative(self, study, trial, search_space):
        if search_space == {}:
            return {}
        # Simulated Annealing algorithm.
        # 1. Calculate transition probability.
        prev_trial = study.trials[-2]
        if self._current_trial is None or prev_trial.value <= self._current_trial.value:</pre>
            probability = 1.0
        else:
            probability = np.exp(
                (self._current_trial.value - prev_trial.value) / self._temperature
            )
        self._temperature *= 0.9 # Decrease temperature.
        # 2. Transit the current state if the previous result is accepted.
        if self._rng.uniform(0, 1) < probability:</pre>
```

```
self._current_trial = prev_trial
       # 3. Sample parameters from the neighborhood of the current point.
       # The sampled parameters will be used during the next execution of
       # the objective function passed to the study.
       params = \{\}
       for param_name, param_distribution in search_space.items():
               not isinstance(param_distribution, optuna.distributions.
→FloatDistribution)
               or (param_distribution.step is not None and param_distribution.step != 1)
               or param_distribution.log
           ):
               msg = (
                    "Only suggest_float() with `step` `None` or 1.0 and"
                   " `log` `False` is supported"
               raise NotImplementedError(msg)
           current_value = self._current_trial.params[param_name]
           width = (param_distribution.high - param_distribution.low) * 0.1
           neighbor_low = max(current_value - width, param_distribution.low)
           neighbor_high = min(current_value + width, param_distribution.high)
           params[param_name] = self._rng.uniform(neighbor_low, neighbor_high)
       return params
   # The rest are unrelated to SA algorithm: boilerplate
   def infer_relative_search_space(self, study, trial):
       return optuna.samplers.intersection_search_space(study)
   def sample_independent(self, study, trial, param_name, param_distribution):
       independent_sampler = optuna.samplers.RandomSampler()
       return independent_sampler.sample_independent(study, trial, param_name, param_
→distribution)
```

Note: In favor of code simplicity, the above implementation doesn't support some features (e.g., maximization). If you're interested in how to support those features, please see examples/samplers/simulated_annealing.py.

You can use SimulatedAnnealingSampler in the same way as built-in samplers as follows:

```
def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    y = trial.suggest_float("y", -5, 5)
    return x**2 + y

sampler = SimulatedAnnealingSampler()
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=100)
```

(continues on next page)

```
best_trial = study.best_trial
print("Best value: ", best_trial.value)
print("Parameters that achieve the best value: ", best_trial.params)
```

Out:

```
Best value: -4.880649841804383 Parameters that achieve the best value: {'x': -0.2882748846691858, 'y': -4. \rightarrow 963752250935415}
```

In this optimization, the values of x and y parameters are sampled by using SimulatedAnnealingSampler. sample_relative method.

Note: Strictly speaking, in the first trial, SimulatedAnnealingSampler.sample_independent method is used to sample parameter values. Because *intersection_search_space()* used in SimulatedAnnealingSampler. infer_relative_search_space cannot infer the search space if there are no complete trials.

Total running time of the script: (0 minutes 0.386 seconds)

User-Defined Pruner

In *optuna.pruners*, we described how an objective function can optionally include calls to a pruning feature which allows Optuna to terminate an optimization trial when intermediate results do not appear promising. In this document, we describe how to implement your own pruner, i.e., a custom strategy for determining when to stop a trial.

Overview of Pruning Interface

The <code>create_study()</code> constructor takes, as an optional argument, a pruner inheriting from <code>BasePruner</code>. The pruner should implement the abstract method <code>prune()</code>, which takes arguments for the associated <code>Study</code> and <code>Trial</code> and returns a boolean value: <code>True</code> if the trial should be pruned and <code>False</code> otherwise. Using the <code>Study</code> and <code>Trial</code> objects, you can access all other trials through the <code>get_trial()</code> method and, and from a trial, its reported intermediate values through the <code>intermediate_values()</code> (a dictionary which maps an integer <code>step</code> to a float value).

You can refer to the source code of the built-in Optuna pruners as templates for building your own. In this document, for illustration, we describe the construction and usage of a simple (but aggressive) pruner which prunes trials that are in last place compared to completed trials at the same step.

Note: Please refer to the documentation of *BasePruner* or, for example, *ThresholdPruner* or *PercentilePruner* for more robust examples of pruner implementation, including error checking and complex pruner-internal logic.

An Example: Implementing LastPlacePruner

We aim to optimize the loss and alpha hyperparameters for a stochastic gradient descent classifier (SGDClassifier) run on the sklearn iris dataset. We implement a pruner which terminates a trial at a certain step if it is in last place compared to completed trials at the same step. We begin considering pruning after a "warmup" of 1 training step and 5 completed trials. For demonstration purposes, we print() a diagnostic message from prune when it is about to return True (indicating pruning).

It may be important to note that the SGDClassifier score, as it is evaluated on a holdout set, decreases with enough training steps due to overfitting. This means that a trial could be pruned even if it had a favorable (high) value on a previous training set. After pruning, Optuna will take the intermediate value last reported as the value of the trial.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.model_selection import train_test_split
from sklearn.linear_model import SGDClassifier
import optuna
from optuna.pruners import BasePruner
from optuna.trial._state import TrialState
class LastPlacePruner(BasePruner):
    def __init__(self, warmup_steps, warmup_trials):
        self._warmup_steps = warmup_steps
        self._warmup_trials = warmup_trials
    def prune(self, study: "optuna.study.Study", trial: "optuna.trial.FrozenTrial") ->_
→bool:
        # Get the latest score reported from this trial
        step = trial.last_step
        if step: # trial.last_step == None when no scores have been reported yet
            this_score = trial.intermediate_values[step]
            # Get scores from other trials in the study reported at the same step
            completed_trials = study.get_trials(deepcopy=False, states=(TrialState.
→COMPLETE.))
            other_scores = [
                t.intermediate_values[step]
                for t in completed_trials
                if step in t.intermediate_values
            other_scores = sorted(other_scores)
            # Prune if this trial at this step has a lower value than all completed.
→trials
            # at the same step. Note that steps will begin numbering at 0 in the.
→objective
            # function definition below.
            if step >= self._warmup_steps and len(other_scores) > self._warmup_trials:
                if this_score < other_scores[0]:</pre>
                    print(f"prune() True: Trial {trial.number}, Step {step}, Score {this_
 score}")
                                                                            (continues on next page)
```

return True

return False

Lastly, let's confirm the implementation is correct with the simple hyperparameter optimization.

```
def objective(trial):
    iris = load_iris()
   classes = np.unique(iris.target)
   X_train, X_valid, y_train, y_valid = train_test_split(
        iris.data, iris.target, train_size=100, test_size=50, random_state=0
   )
   loss = trial.suggest_categorical("loss", ["hinge", "log", "perceptron"])
    alpha = trial.suggest_float("alpha", 0.00001, 0.001, log=True)
   clf = SGDClassifier(loss=loss, alpha=alpha, random_state=0)
    score = 0
    for step in range (0, 5):
        clf.partial_fit(X_train, y_train, classes=classes)
        score = clf.score(X_valid, y_valid)
        trial.report(score, step)
        if trial.should_prune():
            raise optuna.TrialPruned()
   return score
pruner = LastPlacePruner(warmup_steps=1, warmup_trials=5)
study = optuna.create_study(direction="maximize", pruner=pruner)
study.optimize(objective, n_trials=50)
```

Out:

```
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
-site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:

The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
-loss'` which is equivalent.

/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
-site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:

The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
-loss'` which is equivalent.

prune() True: Trial 6, Step 1, Score 0.7
prune() True: Trial 7, Step 4, Score 0.68
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
-site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:
```

```
The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
⇒loss'` which is equivalent.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:
The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
⇒loss'` which is equivalent.
prune() True: Trial 10, Step 1, Score 0.64
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:
The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
→loss'` which is equivalent.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:
The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
→loss'` which is equivalent.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:
The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
→loss'` which is equivalent.
prune() True: Trial 13, Step 2, Score 0.42
prune() True: Trial 18, Step 4, Score 0.68
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:
The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
⇒loss'` which is equivalent.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:
The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
→loss'` which is equivalent.
prune() True: Trial 19, Step 1, Score 0.64
prune() True: Trial 28, Step 4, Score 0.68
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWarning:
The loss 'log' was deprecated in v1.1 and will be removed in version 1.3. Use `loss='log_
→loss'` which is equivalent.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/sklearn/linear_model/_stochastic_gradient.py:173: FutureWaresimgues on next page)
```

Total running time of the script: (0 minutes 0.707 seconds)

Callback for Study.optimize

This tutorial showcases how to use & implement Optuna Callback for optimize().

Callback is called after every evaluation of objective, and it takes *Study* and *FrozenTrial* as arguments, and does some work.

MLflowCallback is a great example.

Stop optimization after some trials are pruned in a row

This example implements a stateful callback which stops the optimization if a certain number of trials are pruned in a row. The number of trials pruned in a row is specified by threshold.

```
class StopWhenTrialKeepBeingPrunedCallback:
    def __init__(self, threshold: int):
        self.threshold = threshold
        self._consequtive_pruned_count = 0

    def __call__(self, study: optuna.study.Study, trial: optuna.trial.FrozenTrial) ->_
        None:
        if trial.state == optuna.trial.TrialState.PRUNED:
            self._consequtive_pruned_count += 1
        else:
            self._consequtive_pruned_count = 0

        if self._consequtive_pruned_count >= self.threshold:
            study.stop()
```

This objective prunes all the trials except for the first 5 trials (trial.number starts with 0).

```
def objective(trial):
    if trial.number > 4:
        raise optuna.TrialPruned
    return trial.suggest_float("x", 0, 1)
```

Here, we set the threshold to 2: optimization finishes once two trials are pruned in a row. So, we expect this study to stop after 7 trials.

```
import logging
import sys

# Add stream handler of stdout to show the messages
optuna.logging.get_logger("optuna").addHandler(logging.StreamHandler(sys.stdout))

study_stop_cb = StopWhenTrialKeepBeingPrunedCallback(2)
study = optuna.create_study()
study.optimize(objective, n_trials=10, callbacks=[study_stop_cb])
```

Out:

```
A new study created in memory with name: no-name-f51ff0b2-a9bf-40d3-a9e5-21e68463cf98

Trial 0 finished with value: 0.9849836959573974 and parameters: {'x': 0.9849836959573974}

Best is trial 0 with value: 0.9849836959573974.

Trial 1 finished with value: 0.47966772409117986 and parameters: {'x': 0.

47966772409117986}. Best is trial 1 with value: 0.47966772409117986.

Trial 2 finished with value: 0.7782737951715811 and parameters: {'x': 0.7782737951715811}

Best is trial 1 with value: 0.47966772409117986.

Trial 3 finished with value: 0.4623593070340617 and parameters: {'x': 0.4623593070340617}

Best is trial 3 with value: 0.4623593070340617.

Trial 4 finished with value: 0.23338949704429202 and parameters: {'x': 0.

23338949704429202}. Best is trial 4 with value: 0.23338949704429202.

Trial 5 pruned.

Trial 6 pruned.
```

As you can see in the log above, the study stopped after 7 trials as expected.

Total running time of the script: (0 minutes 0.008 seconds)

Specify Hyperparameters Manually

It's natural that you have some specific sets of hyperparameters to try first such as initial learning rate values and the number of leaves. Also, it's possible that you've already tried those sets before having Optuna find better sets of hyperparameters.

Optuna provides two APIs to support such cases:

- 1. Passing those sets of hyperparameters and let Optuna evaluate them enqueue_trial()
- 2. Adding the results of those sets as completed Trials add_trial()

First Scenario: Have Optuna evaluate your hyperparameters

In this scenario, let's assume you have some out-of-box sets of hyperparameters but have not evaluated them yet and decided to use Optuna to find better sets of hyperparameters.

Optuna has <code>optuna.study.Study.enqueue_trial()</code> which lets you pass those sets of hyperparameters to Optuna and Optuna will evaluate them.

This section walks you through how to use this lit API with LightGBM.

```
import lightgbm as lgb
import numpy as np
import sklearn.datasets
import sklearn.metrics
from sklearn.model_selection import train_test_split
import optuna
```

Define the objective function.

```
def objective(trial):
   data, target = sklearn.datasets.load_breast_cancer(return_X_y=True)
   train_x, valid_x, train_y, valid_y = train_test_split(data, target, test_size=0.25)
   dtrain = lgb.Dataset(train_x, label=train_y)
   dvalid = lgb.Dataset(valid_x, label=valid_y)
   param = {
        "objective": "binary",
        "metric" "auc".
        "verbosity": -1,
        "boosting_type": "gbdt",
        "bagging_fraction": min(trial.suggest_float("bagging_fraction", 0.4, 1.0 + 1e-
\rightarrow12), 1),
        "bagging_freq": trial.suggest_int("bagging_freq", 0, 7),
        "min_child_samples": trial.suggest_int("min_child_samples", 5, 100),
   }
    # Add a callback for pruning.
   pruning_callback = optuna.integration.LightGBMPruningCallback(trial, "auc")
   gbm = lgb.train(
        param, dtrain, valid_sets=[dvalid], verbose_eval=False, callbacks=[pruning_
→callback]
   )
   preds = gbm.predict(valid_x)
   pred_labels = np.rint(preds)
   accuracy = sklearn.metrics.accuracy_score(valid_y, pred_labels)
   return accuracy
```

Then, construct Study for hyperparameter optimization.

```
study = optuna.create_study(direction="maximize", pruner=optuna.pruners.MedianPruner())
```

Here, we get Optuna evaluate some sets with larger "bagging_fraq" value and the default values.

```
study.enqueue_trial(
        "bagging_fraction": 1.0,
        "bagging_freq": 0,
        "min_child_samples": 20,
   }
)
study.enqueue_trial(
    {
        "bagging_fraction": 0.75,
        "bagging_freq": 5,
        "min_child_samples": 20,
   }
)
import logging
import sys
# Add stream handler of stdout to show the messages to see Optuna works expectedly.
optuna.logging.get_logger("optuna").addHandler(logging.StreamHandler(sys.stdout))
study.optimize(objective, n_trials=100, timeout=600)
```

Out:

```
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 0 finished with value: 0.972027972027972 and parameters: {'bagging_fraction': 1.0,
→ 'bagging_freq': 0, 'min_child_samples': 20}. Best is trial 0 with value: 0.
\rightarrow 972027972027972.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/

→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 1 finished with value: 0.986013986013986 and parameters: {'bagging_fraction': 0.75,
→ 'bagging_freq': 5, 'min_child_samples': 20}. Best is trial 1 with value: 0.
\rightarrow 986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 2 finished with value: 0.972027972027972 and parameters: {'bagging_fraction': 0.
→46185003864730445, 'bagging_freq': 0, 'min_child_samples': 33}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/

→site-packages/lightgbm/engine.py:239: UserWarning:
                                                                            (continues on next page)
```

```
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 3 finished with value: 0.972027972027972 and parameters: {'bagging_fraction': 0.
→9396397986864665, 'bagging_freq': 1, 'min_child_samples': 77}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 4 finished with value: 0.951048951048951 and parameters: {'bagging_fraction': 0.
→6012845245425975, 'bagging_freq': 6, 'min_child_samples': 28}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/

→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of __
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 5 pruned. Trial was pruned at iteration 0.
Trial 6 pruned. Trial was pruned at iteration 0.
Trial 7 pruned. Trial was pruned at iteration 0.
Trial 8 pruned. Trial was pruned at iteration 0.
Trial 9 pruned. Trial was pruned at iteration 0.
Trial 10 pruned. Trial was pruned at iteration 0.
Trial 11 pruned. Trial was pruned at iteration 0.
Trial 12 pruned. Trial was pruned at iteration 0.
Trial 13 pruned. Trial was pruned at iteration 0.
Trial 14 pruned. Trial was pruned at iteration 0.
Trial 15 pruned. Trial was pruned at iteration 0.
Trial 16 pruned. Trial was pruned at iteration 0.
Trial 17 finished with value: 0.951048951048951 and parameters: {'bagging_fraction': 0.
→9256252682754746, 'bagging_freq': 1, 'min_child_samples': 17}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 18 pruned. Trial was pruned at iteration 0.
Trial 19 pruned. Trial was pruned at iteration 0.
Trial 20 pruned. Trial was pruned at iteration 0.
Trial 21 pruned. Trial was pruned at iteration 0.
Trial 22 finished with value: 0.965034965034965 and parameters: {'bagging_fraction': 0.
→7479364651713893, 'bagging_freq': 0, 'min_child_samples': 35}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
```

```
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 23 pruned. Trial was pruned at iteration 0.
Trial 24 finished with value: 0.9790209790209791 and parameters: {'bagging_fraction': 0.
→5186871547183014, 'bagging_freq': 1, 'min_child_samples': 12}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 25 pruned. Trial was pruned at iteration 0.
Trial 26 pruned. Trial was pruned at iteration 0.
Trial 27 pruned. Trial was pruned at iteration 0.
Trial 28 pruned. Trial was pruned at iteration 1.
Trial 29 pruned. Trial was pruned at iteration 0.
Trial 30 finished with value: 0.986013986013986 and parameters: {'bagging_fraction': 0.
→8773825827840325, 'bagging_freq': 1, 'min_child_samples': 11}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 31 pruned. Trial was pruned at iteration 0.
Trial 32 pruned. Trial was pruned at iteration 0.
Trial 33 pruned. Trial was pruned at iteration 0.
Trial 34 pruned. Trial was pruned at iteration 0.
Trial 35 pruned. Trial was pruned at iteration 0.
Trial 36 pruned. Trial was pruned at iteration 0.
Trial 37 pruned. Trial was pruned at iteration 0.
Trial 38 pruned. Trial was pruned at iteration 0.
Trial 39 pruned. Trial was pruned at iteration 0.
Trial 40 pruned. Trial was pruned at iteration 0.
Trial 41 pruned. Trial was pruned at iteration 0.
Trial 42 finished with value: 0.972027972027972 and parameters: {'bagging_fraction': 0.
→44071595886501386, 'bagging_freq': 0, 'min_child_samples': 14}. Best is trial 1 with_
⇒value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 43 pruned. Trial was pruned at iteration 0.
Trial 44 pruned. Trial was pruned at iteration 0.
Trial 45 pruned. Trial was pruned at iteration 0.
Trial 46 pruned. Trial was pruned at iteration 0.
```

(continues on next page)

```
Trial 47 pruned. Trial was pruned at iteration 1.
Trial 48 pruned. Trial was pruned at iteration 0.
Trial 49 pruned. Trial was pruned at iteration 39.
Trial 50 pruned. Trial was pruned at iteration 0.
Trial 51 pruned. Trial was pruned at iteration 0.
Trial 52 pruned. Trial was pruned at iteration 0.
Trial 53 pruned. Trial was pruned at iteration 0.
Trial 54 pruned. Trial was pruned at iteration 0.
Trial 55 finished with value: 0.986013986013986 and parameters: {'bagging_fraction': 0.
→4832542992497587, 'bagging_freq': 0, 'min_child_samples': 25}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/

→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 56 pruned. Trial was pruned at iteration 0.
Trial 57 pruned. Trial was pruned at iteration 0.
Trial 58 pruned. Trial was pruned at iteration 1.
Trial 59 pruned. Trial was pruned at iteration 0.
Trial 60 pruned. Trial was pruned at iteration 0.
Trial 61 pruned. Trial was pruned at iteration 0.
Trial 62 pruned. Trial was pruned at iteration 0.
Trial 63 pruned. Trial was pruned at iteration 0.
Trial 64 finished with value: 0.986013986013986 and parameters: {'bagging_fraction': 0.
→4439809981127098, 'bagging_freq': 0, 'min_child_samples': 13}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/

→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 65 pruned. Trial was pruned at iteration 0.
Trial 66 pruned. Trial was pruned at iteration 0.
Trial 67 pruned. Trial was pruned at iteration 0.
Trial 68 pruned. Trial was pruned at iteration 0.
Trial 69 pruned. Trial was pruned at iteration 0.
Trial 70 pruned. Trial was pruned at iteration 0.
Trial 71 finished with value: 0.9790209790209791 and parameters: {'bagging_fraction': 0.
→9731675392340323, 'bagging_freq': 1, 'min_child_samples': 18}. Best is trial 1 with_
→value: 0.986013986013986.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 72 pruned. Trial was pruned at iteration 0.
Trial 73 pruned. Trial was pruned at iteration 1.
Trial 74 pruned. Trial was pruned at iteration 0.
```

```
Trial 75 pruned. Trial was pruned at iteration 0.
Trial 76 pruned. Trial was pruned at iteration 0.
Trial 77 pruned. Trial was pruned at iteration 54.
Trial 78 pruned. Trial was pruned at iteration 0.
Trial 79 pruned. Trial was pruned at iteration 0.
Trial 80 pruned. Trial was pruned at iteration 0.
Trial 81 pruned. Trial was pruned at iteration 0.
Trial 82 pruned. Trial was pruned at iteration 0.
Trial 83 pruned. Trial was pruned at iteration 0.
Trial 84 pruned. Trial was pruned at iteration 0.
Trial 85 pruned. Trial was pruned at iteration 0.
Trial 86 pruned. Trial was pruned at iteration 0.
Trial 87 pruned. Trial was pruned at iteration 0.
Trial 88 pruned. Trial was pruned at iteration 0.
Trial 89 pruned. Trial was pruned at iteration 0.
Trial 90 pruned. Trial was pruned at iteration 0.
Trial 91 pruned. Trial was pruned at iteration 0.
Trial 92 pruned. Trial was pruned at iteration 0.
Trial 93 pruned. Trial was pruned at iteration 1.
Trial 94 pruned. Trial was pruned at iteration 0.
Trial 95 pruned. Trial was pruned at iteration 0.
Trial 96 pruned. Trial was pruned at iteration 0.
Trial 97 pruned. Trial was pruned at iteration 17.
Trial 98 pruned. Trial was pruned at iteration 0.
Trial 99 pruned. Trial was pruned at iteration 21.
```

Second scenario: Have Optuna utilize already evaluated hyperparameters

In this scenario, let's assume you have some out-of-box sets of hyperparameters and you have already evaluated them but the results are not desirable so that you are thinking of using Optuna.

Optuna has *optuna.study.Study.add_trial()* which lets you register those results to Optuna and then Optuna will sample hyperparameters taking them into account.

In this section, the objective is the same as the first scenario.

```
study = optuna.create_study(direction="maximize", pruner=optuna.pruners.MedianPruner())
study.add_trial(
   optuna.trial.create_trial(
        params={
            "bagging_fraction": 1.0,
            "bagging_freq": 0,
            "min_child_samples": 20.
        },
        distributions={
            "bagging_fraction": optuna.distributions.FloatDistribution(0.4, 1.0 + 1e-12),
            "bagging_freq": optuna.distributions.IntDistribution(0, 7),
            "min_child_samples": optuna.distributions.IntDistribution(5, 100),
        },
        value=0.94,
   )
)
```

(continues on next page)

Out:

```
A new study created in memory with name: no-name-01c15c08-e2bd-451c-b217-19bd90bf75cf
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 2 finished with value: 0.9440559440559441 and parameters: {'bagging_fraction': 0.
→45921771725782745, 'bagging_freq': 7, 'min_child_samples': 9}. Best is trial 1 with_
→value: 0.95.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 3 finished with value: 0.993006993006993 and parameters: {'bagging_fraction': 0.
→4668750230861081, 'bagging_freq': 7, 'min_child_samples': 56}. Best is trial 3 with_
→value: 0.993006993006993.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of ...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 4 finished with value: 0.972027972027972 and parameters: {'bagging_fraction': 0.
→6502201203636713, 'bagging_freq': 5, 'min_child_samples': 72}. Best is trial 3 with
⇒value: 0.993006993006993.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of _
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
```

```
Trial 5 finished with value: 0.9790209790209791 and parameters: {'bagging_fraction': 0.
→932283750537119, 'bagging_freq': 2, 'min_child_samples': 16}. Best is trial 3 with_
→value: 0.993006993006993.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of...
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 6 pruned. Trial was pruned at iteration 2.
Trial 7 pruned. Trial was pruned at iteration 2.
Trial 8 pruned. Trial was pruned at iteration 0.
Trial 9 pruned. Trial was pruned at iteration 0.
Trial 10 pruned. Trial was pruned at iteration 0.
Trial 11 pruned. Trial was pruned at iteration 1.
Trial 12 pruned. Trial was pruned at iteration 1.
Trial 13 pruned. Trial was pruned at iteration 9.
Trial 14 pruned. Trial was pruned at iteration 0.
Trial 15 pruned. Trial was pruned at iteration 4.
Trial 16 pruned. Trial was pruned at iteration 1.
Trial 17 pruned. Trial was pruned at iteration 1.
Trial 18 pruned. Trial was pruned at iteration 38.
Trial 19 pruned. Trial was pruned at iteration 0.
Trial 20 finished with value: 0.9790209790209791 and parameters: {'bagging_fraction': 0.
→6037472800548473, 'bagging_freq': 1, 'min_child_samples': 26}. Best is trial 3 with_
→value: 0.993006993006993.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 21 pruned. Trial was pruned at iteration 2.
Trial 22 pruned. Trial was pruned at iteration 0.
Trial 23 pruned. Trial was pruned at iteration 1.
Trial 24 pruned. Trial was pruned at iteration 0.
Trial 25 pruned. Trial was pruned at iteration 1.
Trial 26 pruned. Trial was pruned at iteration 2.
Trial 27 pruned. Trial was pruned at iteration 1.
Trial 28 pruned. Trial was pruned at iteration 0.
Trial 29 pruned. Trial was pruned at iteration 0.
Trial 30 pruned. Trial was pruned at iteration 0.
Trial 31 pruned. Trial was pruned at iteration 0.
Trial 32 pruned. Trial was pruned at iteration 1.
Trial 33 pruned. Trial was pruned at iteration 0.
Trial 34 pruned. Trial was pruned at iteration 0.
Trial 35 pruned. Trial was pruned at iteration 0.
Trial 36 pruned. Trial was pruned at iteration 1.
Trial 37 pruned. Trial was pruned at iteration 0.
Trial 38 pruned. Trial was pruned at iteration 0.
Trial 39 pruned. Trial was pruned at iteration 0.
```

(continues on next page)

```
Trial 40 pruned. Trial was pruned at iteration 0.
Trial 41 pruned. Trial was pruned at iteration 7.
Trial 42 pruned. Trial was pruned at iteration 1.
Trial 43 pruned. Trial was pruned at iteration 1.
Trial 44 finished with value: 0.9790209790209791 and parameters: {'bagging_fraction': 0.
→9218951296239497, 'bagging_freq': 4, 'min_child_samples': 37}. Best is trial 3 with_
→value: 0.993006993006993.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
⇒site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 45 pruned. Trial was pruned at iteration 1.
Trial 46 pruned. Trial was pruned at iteration 0.
Trial 47 pruned. Trial was pruned at iteration 1.
Trial 48 pruned. Trial was pruned at iteration 1.
Trial 49 pruned. Trial was pruned at iteration 0.
Trial 50 pruned. Trial was pruned at iteration 0.
Trial 51 pruned. Trial was pruned at iteration 0.
Trial 52 pruned. Trial was pruned at iteration 0.
Trial 53 pruned. Trial was pruned at iteration 1.
Trial 54 pruned. Trial was pruned at iteration 1.
Trial 55 pruned. Trial was pruned at iteration 1.
Trial 56 pruned. Trial was pruned at iteration 0.
Trial 57 pruned. Trial was pruned at iteration 0.
Trial 58 pruned. Trial was pruned at iteration 2.
Trial 59 pruned. Trial was pruned at iteration 0.
Trial 60 pruned. Trial was pruned at iteration 0.
Trial 61 pruned. Trial was pruned at iteration 0.
Trial 62 pruned. Trial was pruned at iteration 0.
Trial 63 pruned. Trial was pruned at iteration 0.
Trial 64 pruned. Trial was pruned at iteration 0.
Trial 65 pruned. Trial was pruned at iteration 1.
Trial 66 pruned. Trial was pruned at iteration 0.
Trial 67 pruned. Trial was pruned at iteration 1.
Trial 68 pruned. Trial was pruned at iteration 0.
Trial 69 pruned. Trial was pruned at iteration 0.
Trial 70 pruned. Trial was pruned at iteration 0.
Trial 71 pruned. Trial was pruned at iteration 97.
Trial 72 pruned. Trial was pruned at iteration 1.
Trial 73 pruned. Trial was pruned at iteration 0.
Trial 74 finished with value: 0.993006993006993 and parameters: {'bagging_fraction': 0.
→8353625609741543, 'bagging_freq': 1, 'min_child_samples': 71}. Best is trial 3 with
→value: 0.993006993006993.
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/

→site-packages/lightgbm/engine.py:239: UserWarning:
'verbose_eval' argument is deprecated and will be removed in a future release of
→LightGBM. Pass 'log_evaluation()' callback via 'callbacks' argument instead.
Trial 75 pruned. Trial was pruned at iteration 0.
```

```
Trial 76 pruned. Trial was pruned at iteration 0.
Trial 77 pruned. Trial was pruned at iteration 0.
Trial 78 pruned. Trial was pruned at iteration 0.
Trial 79 pruned. Trial was pruned at iteration 0.
Trial 80 pruned. Trial was pruned at iteration 0.
Trial 81 pruned. Trial was pruned at iteration 0.
Trial 82 pruned. Trial was pruned at iteration 0.
Trial 83 pruned. Trial was pruned at iteration 0.
Trial 84 pruned. Trial was pruned at iteration 0.
Trial 85 pruned. Trial was pruned at iteration 0.
Trial 86 pruned. Trial was pruned at iteration 0.
Trial 87 pruned. Trial was pruned at iteration 0.
Trial 88 pruned. Trial was pruned at iteration 0.
Trial 89 pruned. Trial was pruned at iteration 0.
Trial 90 pruned. Trial was pruned at iteration 0.
Trial 91 pruned. Trial was pruned at iteration 0.
Trial 92 pruned. Trial was pruned at iteration 0.
Trial 93 pruned. Trial was pruned at iteration 1.
Trial 94 pruned. Trial was pruned at iteration 1.
Trial 95 pruned. Trial was pruned at iteration 0.
Trial 96 pruned. Trial was pruned at iteration 0.
Trial 97 pruned. Trial was pruned at iteration 0.
Trial 98 pruned. Trial was pruned at iteration 0.
Trial 99 pruned. Trial was pruned at iteration 0.
Trial 100 pruned. Trial was pruned at iteration 0.
Trial 101 pruned. Trial was pruned at iteration 1.
```

Total running time of the script: (0 minutes 6.992 seconds)

Ask-and-Tell Interface

Optuna has an *Ask-and-Tell* interface, which provides a more flexible interface for hyperparameter optimization. This tutorial explains three use-cases when the ask-and-tell interface is beneficial:

- Apply Optuna to an existing optimization problem with minimum modifications
- Define-and-Run
- Batch Optimization

Apply Optuna to an existing optimization problem with minimum modifications

Let's consider the traditional supervised classification problem; you aim to maximize the validation accuracy. To do so, you train *LogisticRegression* as a simple model.

```
import numpy as np
from sklearn.datasets import make_classification
from sklearn.linear_model import LogisticRegression
from sklearn.model_selection import train_test_split
import optuna
```

(continues on next page)

```
X, y = make_classification(n_features=10)
X_train, X_test, y_train, y_test = train_test_split(X, y)

C = 0.01
clf = LogisticRegression(C=C)
clf.fit(X_train, y_train)
val_accuracy = clf.score(X_test, y_test) # the objective
```

Then you try to optimize hyperparameters C and solver of the classifier by using optuna. When you introduce optuna naively, you define an objective function such that it takes trial and calls suggest_* methods of trial to sample the hyperparameters:

```
def objective(trial):
    X, y = make_classification(n_features=10)
    X_train, X_test, y_train, y_test = train_test_split(X, y)

C = trial.suggest_float("C", 1e-7, 10.0, log=True)
    solver = trial.suggest_categorical("solver", ("lbfgs", "saga"))

clf = LogisticRegression(C=C, solver=solver)
    clf.fit(X_train, y_train)
    val_accuracy = clf.score(X_test, y_test)

    return val_accuracy

study = optuna.create_study(direction="maximize")
study.optimize(objective, n_trials=10)
```

Out:

```
/home/docs/checkouts/readthedocs.org/user_builds/optuna/envs/v3.0.0-b0/lib/python3.8/
—site-packages/sklearn/linear_model/_sag.py:350: ConvergenceWarning:

The max_iter was reached which means the coef_ did not converge
```

This interface is not flexible enough. For example, if objective requires additional arguments other than trial, you need to define a class as in How to define objective functions that have own arguments?. The ask-and-tell interface provides a more flexible syntax to optimize hyperparameters. The following example is equivalent to the previous code block.

```
study = optuma.create_study(direction="maximize")

n_trials = 10
for _ in range(n_trials):
    trial = study.ask()  # `trial` is a `Trial` and not a `FrozenTrial`.

C = trial.suggest_float("C", 1e-7, 10.0, log=True)
    solver = trial.suggest_categorical("solver", ("lbfgs", "saga"))

clf = LogisticRegression(C=C, solver=solver)
    clf.fit(X_train, y_train)
```

57

```
val_accuracy = clf.score(X_test, y_test)
study.tell(trial, val_accuracy) # tell the pair of trial and objective value
```

The main difference is to use two methods: <code>optuna.study.Study.ask()</code> and <code>optuna.study.Study.tell()</code>. <code>optuna.study.Study.ask()</code> creates a trial that can sample hyperparameters, and <code>optuna.study.Study.tell()</code> finishes the trial by passing trial and an objective value. You can apply Optuna's hyperparameter optimization to your original code without an objective function.

If you want to make your optimization faster with a pruner, you need to explicitly pass the state of trial to the argument of <code>optuna.study.Study.tell()</code> method as follows:

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)
n_train_iter = 100
# define study with hyperband pruner.
study = optuna.create_study(
   direction="maximize",
   pruner=optuna.pruners.HyperbandPruner(
        min_resource=1, max_resource=n_train_iter, reduction_factor=3
   ),
)
for _ in range(20):
   trial = study.ask()
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
   clf = SGDClassifier(alpha=alpha)
   pruned_trial = False
    for step in range(n_train_iter):
        clf.partial_fit(X_train, y_train, classes=classes)
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step)
        if trial.should_prune():
            pruned trial = True
            break
    if pruned_trial:
        study.tell(trial, state=optuna.trial.TrialState.PRUNED) # tell the pruned state
                                                                            (continues on next page)
```

```
else:
    score = clf.score(X_valid, y_valid)
    study.tell(trial, score) # tell objective value
```

Note: optuna.study.Study.tell() method can take a trial number rather than the trial object. study.tell(trial.number, y) is equivalent to study.tell(trial, y).

Define-and-Run

The ask-and-tell interface supports both *define-by-run* and *define-and-run* APIs. This section shows the example of the *define-and-run* API in addition to the define-by-run example above.

Define distributions for the hyperparameters before calling the *optuna.study.Study.ask()* method for define-and-run API. For example,

```
distributions = {
    "C": optuma.distributions.FloatDistribution(1e-7, 10.0, log=True),
    "solver": optuma.distributions.CategoricalDistribution(("lbfgs", "saga")),
}
```

Pass distributions to *optuna.study.Study.ask()* method at each call. The retuned trial contains the suggested hyperparameters.

```
study = optuna.create_study(direction="maximize")
n_trials = 10
for _ in range(n_trials):
    trial = study.ask(distributions) # pass the pre-defined distributions.

# two hyperparameters are already sampled from the pre-defined distributions
C = trial.params["C"]
solver = trial.params["solver"]

clf = LogisticRegression(C=C, solver=solver)
clf.fit(X_train, y_train)
val_accuracy = clf.score(X_test, y_test)

study.tell(trial, val_accuracy)
```

Batch Optimization

The ask-and-tell interface enables us to optimize a batched objective for faster optimization. For example, parallelizable evaluation, operation over vectors, etc.

The following objective takes batched hyperparameters xs and ys instead of a single pair of hyperparameters x and y and calculates the objective over the full vectors.

```
def batched_objective(xs: np.ndarray, ys: np.ndarray):
   return xs**2 + ys
```

In the following example, the number of pairs of hyperparameters in a batch is 10, and batched_objective is evaluated three times. Thus, the number of trials is 30. Note that you need to store either trial_ids or trial to call optuna.study.Study.tell() method after the batched evaluations.

```
batch_size = 10
study = optuna.create_study(sampler=optuna.samplers.CmaEsSampler())
for _ in range(3):
    # create batch
   trial_ids = []
   x_batch = []
   y_batch = []
    for _ in range(batch_size):
        trial = study.ask()
        trial_ids.append(trial.number)
        x_batch.append(trial.suggest_float("x", -10, 10))
        y_batch.append(trial.suggest_float("y", -10, 10))
    # evaluate batched objective
   x_batch = np.array(x_batch)
   y_batch = np.array(y_batch)
   objectives = batched_objective(x_batch, y_batch)
    # finish all trials in the batch
    for trial_id, objective in zip(trial_ids, objectives):
        study tell(trial_id, objective)
```

Total running time of the script: (0 minutes 0.119 seconds)

Re-use the best trial

In some cases, you may want to re-evaluate the objective function with the best hyperparameters again after the hyperparameter optimization.

For example,

- You have found good hyperparameters with Optuna and want to run a similar *objective* function using the best hyperparameters found so far to further analyze the results, or
- You have optimized with Optuna using a partial dataset to reduce training time. After the hyperparameter tuning, you want to train the model using the whole dataset with the best hyperparameter values found.

best_trial provides an interface to re-evaluate the objective function with the current best hyperparameter values.

This tutorial shows an example of how to re-run a different *objective* function with the current best values, like the first example above.

Investigating the best model further

Let's consider a classical supervised classification problem with Optuna as follows:

```
from sklearn import metrics
from sklearn.datasets import make_classification
from sklearn.linear_model import LogisticRegression
from sklearn.model_selection import train_test_split

import optuna

def objective(trial):
    X, y = make_classification(n_features=10, random_state=1)
    X_train, X_test, y_train, y_test = train_test_split(X, y, random_state=1)

    C = trial.suggest_float("C", 1e-7, 10.0, log=True)
    clf = LogisticRegression(C=C)
    clf.fit(X_train, y_train)
    return clf.score(X_test, y_test)

study = optuna.create_study(direction="maximize")
study.optimize(objective, n_trials=10)
print(study.best_trial.value) # Show the best value.
```

Out:

```
0.92
```

Suppose after the hyperparameter optimization, you want to calculate other evaluation metrics such as recall, precision, and f1-score on the same dataset. You can define another objective function that shares most of the objective function to reproduce the model with the best hyperparameters.

```
def detailed_objective(trial):
    # Use same code objective to reproduce the best model
    X, y = make_classification(n_features=10, random_state=1)
    X_train, X_test, y_train, y_test = train_test_split(X, y, random_state=1)

C = trial.suggest_float("C", 1e-7, 10.0, log=True)

clf = LogisticRegression(C=C)
    clf.fit(X_train, y_train)

# calculate more evaluation metrics
    pred = clf.predict(X_test)

acc = metrics.accuracy_score(pred, y_test)
    recall = metrics.recall_score(pred, y_test)
```

```
precision = metrics.precision_score(pred, y_test)
f1 = metrics.f1_score(pred, y_test)
return acc, f1, recall, precision
```

Pass study.best_trial as the argument of detailed_objective.

```
detailed_objective(study.best_trial) # calculate acc, f1, recall, and precision
```

Out:

```
(0.92, 0.9285714285714286, 0.9285714285714286, 0.9285714285714286)
```

The difference between best_trial and ordinal trials

This uses <code>best_trial</code>, which returns the <code>best_trial</code> as a <code>FrozenTrial</code>. The <code>FrozenTrial</code> is different from an active trial and behaves differently from <code>Trial</code> in some situations. For example, pruning does not work because <code>should_prune</code> always returns <code>False</code>.

Note: For multi-objective optimization as demonstrated by *Multi-objective Optimization with Optuna*, *best_trials* returns a list of *FrozenTrial* on Pareto front. So we can re-use each trial in the list by the similar way above.

Total running time of the script: (0 minutes 0.052 seconds)

6.3 API Reference

6.3.1 optuna

The *optuna* module is primarily used as an alias for basic Optuna functionality coded in other modules. Currently, two modules are aliased: (1) from *optuna.study*, functions regarding the Study lifecycle, and (2) from *optuna.exceptions*, the TrialPruned Exception raised when a trial is pruned.

optuna.create_study	Create a new <i>Study</i> .
optuna.load_study	Load the existing <i>Study</i> that has the specified name.
optuna.delete_study	Delete a Study object.
optuna.copy_study	Copy study from one storage to another.
optuna.get_all_study_summaries	Get all history of studies stored in a specified storage.
optuna.TrialPruned	Exception for pruned trials.

6.3. API Reference 61

optuna.create study

optuna.create_study(*, storage=None, sampler=None, pruner=None, study_name=None, direction=None, load_if_exists=False, directions=None)

Create a new Study.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", 0, 10)
    return x**2

study = optuna.create_study()
study.optimize(objective, n_trials=3)
```

Parameters

• **storage** (Optional [Union [str, optuna.storages._base.BaseStorage]]) — Database URL. If this argument is set to None, in-memory storage is used, and the Study will not be persistent.

Note:

When a database URL is passed, Optuna internally uses SQLAlchemy to handle the database. Please refer to SQLAlchemy's document for further details. If you want to specify non-default options to SQLAlchemy Engine, you can instantiate *RDBStorage* with your desired options and pass it to the storage argument instead of a URL.

- sampler (Optional [optuna.samplers._base.BaseSampler]) A sampler object that implements background algorithm for value suggestion. If None is specified, TPESampler is used during single-objective optimization and NSGAIISampler during multi-objective optimization. See also samplers.
- **pruner** (Optional[optuna.pruners._base.BasePruner]) A pruner object that decides early stopping of unpromising trials. If None is specified, MedianPruner is used as the default. See also pruners.
- **study_name** (*Optional[str]*) Study's name. If this argument is set to None, a unique name is generated automatically.
- direction (Optional[Union[str, optuna.study._study_direction. StudyDirection]]) - Direction of optimization. Set minimize for minimization and maximize for maximization. You can also pass the corresponding StudyDirection object.

Note: If none of *direction* and *directions* are specified, the direction of the study is set to "minimize".

- load_if_exists (bool) Flag to control the behavior to handle a conflict of study names. In the case where a study named study_name already exists in the storage, a <code>DuplicatedStudyError</code> is raised if load_if_exists is set to False. Otherwise, the creation of the study is skipped, and the existing one is returned.
- directions (Optional[Sequence[Union[str, optuna.study. _study_direction.StudyDirection]]]) - A sequence of directions during multi-objective optimization.

Returns A Study object.

Raises ValueError – If the length of directions is zero. Or, if direction is neither 'minimize' nor 'maximize' when it is a string. Or, if the element of directions is neither *minimize* nor *maximize*. Or, if both direction and directions are specified.

Return type optuna.study.study.Study

See also:

```
optuna.create_study() is an alias of optuna.study.create_study().
```

See also:

The Saving/Resuming Study with RDB Backend tutorial provides concrete examples to save and resume optimization using RDB.

optuna.load_study

```
optuna.load_study(*, study_name, storage, sampler=None, pruner=None)
```

Load the existing *Study* that has the specified name.

Example

Parameters

- **study_name** (Optional[str]) Study's name. Each study has a unique name as an identifier. If None, checks whether the storage contains a single study, and if so loads that study.
- **storage** (*Union[str, optuna.storages._base.BaseStorage]*) Database URL such as sqlite:///example.db. Please see also the documentation of *create_study()* for further details.

6.3. API Reference 63

- **sampler** (Optional [optuna.samplers._base.BaseSampler]) A sampler object that implements background algorithm for value suggestion. If None is specified, TPESampler is used as the default. See also samplers.
- **pruner** (Optional [optuna.pruners._base.BasePruner]) A pruner object that decides early stopping of unpromising trials. If None is specified, MedianPruner is used as the default. See also pruners.

Raises ValueError – If study_name is None and the storage contains more than 1 study.

Return type optuna.study.study.Study

See also:

optuna.load_study() is an alias of optuna.study.load_study().

optuna.delete study

```
optuna.delete_study(*, study_name, storage)
```

Delete a Study object.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

study = optuna.create_study(study_name="example-study", storage="sqlite:///example.
    db")
study.optimize(objective, n_trials=3)

optuna.delete_study(study_name="example-study", storage="sqlite:///example.db")
```

Parameters

- **study_name** (*str*) Study's name.
- **storage** (*Union[str, optuma.storages._base.BaseStorage]*) Database URL such as sqlite:///example.db. Please see also the documentation of *create_study()* for further details.

Return type None

See also:

```
optuna.delete_study() is an alias of optuna.study.delete_study().
```

optuna.copy study

```
optuna.copy_study(*, from_study_name, from_storage, to_storage, to_study_name=None)
Copy study from one storage to another.
```

The direction(s) of the objective(s) in the study, trials, user attributes and system attributes are copied.

Note: *copy_study()* copies a study even if the optimization is working on. It means users will get a copied study that contains a trial that is not finished.

Example

```
import optuna
def objective(trial):
   x = trial.suggest_float("x", -10, 10)
   return (x - 2) ** 2
study = optuna.create_study(
    study_name="example-study",
    storage="sqlite:///example.db",
study optimize(objective, n_trials=3)
optuna.copy_study(
    from_study_name="example-study",
    from_storage="sqlite:///example.db",
    to_storage="sqlite:///example_copy.db",
)
study = optuna.load_study(
    study_name=None,
    storage="sqlite:///example_copy.db",
)
```

Parameters

- **from_study_name** (*str*) Name of study.
- from_storage (Union[str, optuma.storages._base.BaseStorage]) Source
 database URL such as sqlite:///example.db. Please see also the documentation of
 create_study() for further details.
- to_storage (Union[str, optuna.storages._base.BaseStorage]) Destination database URL.
- to_study_name (Optional[str]) Name of the created study. If omitted, from_study_name is used.

Raises *DuplicatedStudyError* – If a study with a conflicting name already exists in the destination storage.

6.3. API Reference 65

Return type None

optuna.get_all_study_summaries

```
\verb"optuna.get_all_study_summaries" ( \textit{storage}, include\_best\_trial = True)
```

Get all history of studies stored in a specified storage.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

study = optuna.create_study(study_name="example-study", storage="sqlite:///example.
    db")
study.optimize(objective, n_trials=3)

study_summaries = optuna.study.get_all_study_summaries(storage="sqlite:///example.db
    "")
assert len(study_summaries) == 1

study_summary = study_summaries[0]
assert study_summary.study_name == "example-study"
```

Parameters

- **storage** (*Union[str, optuna.storages._base.BaseStorage]*) Database URL such as sqlite:///example.db. Please see also the documentation of *create_study()* for further details.
- **include_best_trial** (*bool*) Include the best trials if exist. It potentially increases the number of queries and may take longer to fetch summaries depending on the storage.

Returns List of study history summarized as *StudySummary* objects.

Return type *List*[optuna.study._study_summary.StudySummary]

See also:

```
optuna.get_all_study_summaries() is an alias of optuna.study.get_all_study_summaries().
```

optuna.TrialPruned

exception optuna.TrialPruned

Exception for pruned trials.

This error tells a trainer that the current *Trial* was pruned. It is supposed to be raised after *optuna.trial*. *Trial.should_prune()* as shown in the following example.

See also:

optuna. TrialPruned is an alias of optuna. exceptions. TrialPruned.

Example

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)
def objective(trial):
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
    clf = SGDClassifier(alpha=alpha)
   n_train_iter = 100
    for step in range(n_train_iter):
        clf.partial_fit(X_train, y_train, classes=classes)
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step)
        if trial.should_prune():
            raise optuna.TrialPruned()
   return clf.score(X_valid, y_valid)
study = optuna.create_study(direction="maximize")
study.optimize(objective, n_trials=20)
```

6.3. API Reference 67

6.3.2 optuna.cli

The *cli* module implements Optuna's command-line functionality using the cliff framework.

See also:

The Command-Line Interface tutorial provides use-cases with examples.

```
optuna
    [--version]
    [-v | -q]
    [--log-file LOG_FILE]
    [--debug]
    [--storage STORAGE]
```

--version

show program's version number and exit

-v, --verbose

Increase verbosity of output. Can be repeated.

-q, --quiet

Suppress output except warnings and errors.

```
--log-file <LOG_FILE>
```

Specify a file to log output. Disabled by default.

--debug

Show tracebacks on errors.

--storage <STORAGE>

DB URL. (e.g. sqlite:///example.db)

ask

Create a new trial and suggest parameters.

```
optuna ask
    [--study-name STUDY_NAME]
    [--direction {minimize,maximize}]
    [--directions {minimize,maximize} [{minimize,maximize} ...]]
    [--sampler SAMPLER]
    [--sampler-kwargs SAMPLER_KWARGS]
    [--search-space SEARCH_SPACE]
    [-f {json,table,yaml}]
    [--flatten]
```

--study-name <STUDY_NAME>

Name of study.

--direction <DIRECTION>

Direction of optimization. This argument is deprecated. Please create a study in advance.

--directions <DIRECTIONS>

Directions of optimization, if there are multiple objectives. This argument is deprecated. Please create a study in advance.

--sampler <SAMPLER>

Class name of sampler object to create.

--sampler-kwargs <SAMPLER_KWARGS>

Sampler object initialization keyword arguments as JSON.

--search-space <SEARCH_SPACE>

Search space as JSON. Keys are names and values are outputs from <code>distribution_to_json()</code>.

```
-f <FORMAT>, --format <FORMAT>
   Output format.
```

--flatten

Flatten nested columns such as params.

This command is provided by the optuna plugin.

best-trial

Show the best trial.

```
optuna best-trial
   --study-name STUDY_NAME
   [-f {json,table,yaml}]
   [--flatten]
```

--study-name <STUDY_NAME>

The name of the study to get the best trial.

```
-f <FORMAT>, --format <FORMAT>
   Output format.
```

--flatten

Flatten nested columns such as params and user_attrs.

This command is provided by the optuna plugin.

best-trials

Show a list of trials located at the Pareto front.

```
optuna best-trials
   --study-name STUDY_NAME
   [-f {json,table,yaml}]
   [--flatten]
```

--study-name <STUDY_NAME>

The name of the study to get the best trials (trials at the Pareto front).

```
-f <FORMAT>, --format <FORMAT>
   Output format.
```

--flatten

Flatten nested columns such as params and user_attrs.

This command is provided by the optuna plugin.

create-study

Create a new study.

```
optuna create-study
   [--study-name STUDY_NAME]
   [--direction {minimize,maximize}]
   [--skip-if-exists]
   [--directions {minimize,maximize} [{minimize,maximize} ...]]
```

--study-name <STUDY_NAME>

A human-readable name of a study to distinguish it from others.

--direction <DIRECTION>

Set direction of optimization to a new study. Set 'minimize' for minimization and 'maximize' for maximization.

--skip-if-exists

If specified, the creation of the study is skipped without any error when the study name is duplicated.

--directions <DIRECTIONS>

Set directions of optimization to a new study. Put whitespace between directions. Each direction should be either "minimize" or "maximize".

This command is provided by the optuna plugin.

delete-study

Delete a specified study.

```
optuna delete-study [--study-name STUDY_NAME]
```

--study-name <STUDY_NAME>

The name of the study to delete.

This command is provided by the optuna plugin.

storage upgrade

Upgrade the schema of a storage.

```
optuna storage upgrade
```

This command is provided by the optuna plugin.

studies

70

Show a list of studies.

```
optuna studies [-f {json,table,yaml}] [--flatten]
```

```
\textbf{-f} < \!\! \texttt{FORMAT} \!\! > \!\! , \ \textbf{--format} < \!\! \texttt{FORMAT} \!\! >
```

Output format.

--flatten

Flatten nested columns such as directions.

This command is provided by the optuna plugin.

study optimize

Start optimization of a study. Deprecated since version 2.0.0.

```
optuna study optimize
    [--n-trials N_TRIALS]
    [--timeout TIMEOUT]
    [--n-jobs N_JOBS]
    [--study STUDY]
    [--study-name STUDY_NAME]
    file
    method
```

--n-trials <N_TRIALS>

The number of trials. If this argument is not given, as many trials run as possible.

--timeout <TIMEOUT>

Stop study after the given number of second(s). If this argument is not given, as many trials run as possible.

```
--n-jobs <N_JOBS>
```

The number of parallel jobs. If this argument is set to -1, the number is set to CPU counts.

```
--study <STUDY>
```

This argument is deprecated. Use -study-name instead.

```
--study-name <STUDY_NAME>
```

The name of the study to start optimization on.

file

Python script file where the objective function resides.

method

The method name of the objective function.

This command is provided by the optuna plugin.

study set-user-attr

Set a user attribute to a study.

```
optuna study set-user-attr
[--study STUDY]
[--study-name STUDY_NAME]
--key KEY
--value VALUE
```

--study <STUDY>

This argument is deprecated. Use -study-name instead.

```
--study-name <STUDY_NAME>
```

The name of the study to set the user attribute to.

```
--key <KEY>, -k <KEY>
```

Key of the user attribute.

```
--value <VALUE>, -v <VALUE>
```

Value to be set.

This command is provided by the optuna plugin.

tell

Finish a trial, which was created by the ask command.

```
optuna tell
    [--study-name STUDY_NAME]
    [--trial-number TRIAL_NUMBER]
    [--values VALUES [VALUES ...]]
    [--state {complete,pruned,fail}]
    [--skip-if-finished]
```

```
--study-name <STUDY_NAME>
```

Name of study.

--trial-number <TRIAL_NUMBER>

Trial number.

--values <VALUES>

Objective values.

--state <STATE>

Trial state.

--skip-if-finished

If specified, tell is skipped without any error when the trial is alreadyfinished.

This command is provided by the optuna plugin.

trials

Show a list of trials.

```
optuna trials
   --study-name STUDY_NAME
   [-f {json,table,yaml}]
   [--flatten]
```

```
--study-name <STUDY_NAME>
```

The name of the study which includes trials.

```
-f <FORMAT>, --format <FORMAT>
```

Output format.

--flatten

Flatten nested columns such as params and user_attrs.

This command is provided by the optuna plugin.

6.3.3 optuna.distributions

The *distributions* module defines various classes representing probability distributions, mainly used to suggest initial hyperparameter values for an optimization trial. Distribution classes inherit from a library-internal BaseDistribution, and is initialized with specific parameters, such as the low and high endpoints for a *IntDistribution*.

Optuna users should not use distribution classes directly, but instead use utility functions provided by *Trial* such as *suggest_int()*.

optuna.distributions.FloatDistribution	A distribution on floats.
optuna.distributions.IntDistribution	A distribution on integers.
optuna.distributions.UniformDistribution	A uniform distribution in the linear domain.
optuna.distributions.	A uniform distribution in the log domain.
LogUniformDistribution	
optuna.distributions.	A discretized uniform distribution in the linear domain.
DiscreteUniformDistribution	
optuna.distributions.	A uniform distribution on integers.
IntUniformDistribution	
optuna.distributions.	A uniform distribution on integers in the log domain.
IntLogUniformDistribution	
optuna.distributions.	A categorical distribution.
CategoricalDistribution	
optuna.distributions.distribution_to_json	Serialize a distribution to JSON format.
optuna.distributions.json_to_distribution	Deserialize a distribution in JSON format.
optuna.distributions.	A function to check compatibility of two distributions.
<pre>check_distribution_compatibility</pre>	

optuna.distributions.FloatDistribution

class optuna.distributions.**FloatDistribution**(low, high, log=False, step=None)

A distribution on floats.

This object is instantiated by suggest_float(), and passed to samplers in general.

Note: When step is not None, if the range [low, high] is not divisible by step, high will be replaced with the maximum of $k \times \text{step} + \text{low} < \text{high}$, where k is an integer.

low

Lower endpoint of the range of the distribution. low is included in the range.

high

Upper endpoint of the range of the distribution. high is included in the range.

log

If log is True, this distribution is in log-scaled domain.

step

A discretization step. This parameter must be None when the parameter log is True.

Raises ValueError – If low value is larger than high value. If log is True and low value is less or equal to 0.0. If log is True and step is not None. If step is less or equal to 0.

Parameters

- low (float) -
- high (float) -
- log (bool) -
- step (Union[None, float]) -

Return type None

Methods

single()	Test whether the range of this distribution contains
	just a single value.
to_external_repr(param_value_in_internal_repr)	Convert internal representation of a parameter value
	into external representation.
to_internal_repr(param_value_in_external_repr)	Convert external representation of a parameter value
	into internal representation.

single()

Test whether the range of this distribution contains just a single value.

Returns True if the range of this distribution contains just a single value, otherwise False.

Return type bool

to_external_repr(param value in internal repr)

Convert internal representation of a parameter value into external representation.

Parameters param_value_in_internal_repr (*float*) – Optuna's internal representation of a parameter value.

Returns Optuna's external representation of a parameter value.

Return type Any

to_internal_repr(param_value_in_external_repr)

Convert external representation of a parameter value into internal representation.

Parameters param_value_in_external_repr (*Any*) – Optuna's external representation of a parameter value.

Returns Optuna's internal representation of a parameter value.

Return type float

optuna.distributions.IntDistribution

class optuna.distributions.IntDistribution(low, high, log=False, step=1)

A distribution on integers.

This object is instantiated by suggest_int(), and passed to samplers in general.

Note: When step is not None, if the range [low, high] is not divisible by step, high will be replaced with the maximum of $k \times \text{step} + \text{low} < \text{high}$, where k is an integer.

low

Lower endpoint of the range of the distribution. low is included in the range.

high

Upper endpoint of the range of the distribution. high is included in the range.

log

If log is True, this distribution is in log-scaled domain.

step

A discretization step. This parameter must be 1 when the parameter log is True.

Raises ValueError – If low value is larger than high value. If low value is less than 1 when log is True. If step is not positive value. If log is True and step!= 1.

Parameters

- low (int) -
- high (int) -
- log (bool) -
- **step** (*int*) -

Return type None

Methods

single()	Test whether the range of this distribution contains
	just a single value.
to_external_repr(param_value_in_internal_repr)	Convert internal representation of a parameter value
	into external representation.
to_internal_repr(param_value_in_external_repr)	Convert external representation of a parameter value
	into internal representation.

single()

Test whether the range of this distribution contains just a single value.

Returns True if the range of this distribution contains just a single value, otherwise False.

Return type bool

to_external_repr(param_value_in_internal_repr)

Convert internal representation of a parameter value into external representation.

Parameters param_value_in_internal_repr (*float*) – Optuna's internal representation of a parameter value.

Returns Optuna's external representation of a parameter value.

Return type int

to_internal_repr(param_value_in_external_repr)

Convert external representation of a parameter value into internal representation.

Parameters param_value_in_external_repr (*int*) – Optuna's external representation of a parameter value.

Returns Optuna's internal representation of a parameter value.

Return type float

optuna.distributions.UniformDistribution

class optuna.distributions.UniformDistribution(low, high)

A uniform distribution in the linear domain.

This object is instantiated by suggest_float(), and passed to samplers in general.

low

Lower endpoint of the range of the distribution. low is included in the range.

hiah

Upper endpoint of the range of the distribution. high is included in the range.

Raises ValueError – If low value is larger than high value.

Parameters

- low (float) -
- high (float) -

Return type None

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use FloatDistribution instead.

Methods

single()	Test whether the range of this distribution contains
	just a single value.
to_external_repr(param_value_in_internal_repr)	Convert internal representation of a parameter value
	into external representation.
to_internal_repr(param_value_in_external_repr)	Convert external representation of a parameter value
	into internal representation.

single()

Test whether the range of this distribution contains just a single value.

Returns True if the range of this distribution contains just a single value, otherwise False.

Return type bool

to_external_repr(param_value_in_internal_repr)

Convert internal representation of a parameter value into external representation.

Parameters param_value_in_internal_repr (*float*) – Optuna's internal representation of a parameter value.

Returns Optuna's external representation of a parameter value.

Return type Any

to_internal_repr(param_value_in_external_repr)

Convert external representation of a parameter value into internal representation.

Parameters param_value_in_external_repr (*Any*) – Optuna's external representation of a parameter value.

Returns Optuna's internal representation of a parameter value.

Return type float

optuna.distributions.LogUniformDistribution

class optuna.distributions.LogUniformDistribution(low, high)

A uniform distribution in the log domain.

This object is instantiated by <code>suggest_float()</code> with <code>log=True</code>, and passed to <code>samplers</code> in general.

low

Lower endpoint of the range of the distribution. low is included in the range.

high

Upper endpoint of the range of the distribution. high is included in the range.

Raises ValueError – If low value is larger than high value, or low value is smaller than or equal to 0.

Parameters

- low (float) -
- high (float) -

Return type None

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use FloatDistribution instead.

Methods

single()	Test whether the range of this distribution contains
	just a single value.
to_external_repr(param_value_in_internal_repr)	Convert internal representation of a parameter value
	into external representation.
to_internal_repr(param_value_in_external_repr)	Convert external representation of a parameter value
	into internal representation.

single()

Test whether the range of this distribution contains just a single value.

Returns True if the range of this distribution contains just a single value, otherwise False.

Return type bool

to_external_repr(param_value_in_internal_repr)

Convert internal representation of a parameter value into external representation.

Parameters param_value_in_internal_repr (*float*) – Optuna's internal representation of a parameter value.

Returns Optuna's external representation of a parameter value.

Return type Any

to_internal_repr(param_value_in_external_repr)

Convert external representation of a parameter value into internal representation.

Parameters param_value_in_external_repr (*Any*) – Optuna's external representation of a parameter value.

Returns Optuna's internal representation of a parameter value.

Return type float

optuna.distributions.DiscreteUniformDistribution

class optuna.distributions.DiscreteUniformDistribution(low, high, q)

A discretized uniform distribution in the linear domain.

This object is instantiated by suggest_float() with step argument, and passed to samplers in general.

Note: If the range [low, high] is not divisible by q, high will be replaced with the maximum of kq + low < high, where k is an integer.

Parameters

- low (float) Lower endpoint of the range of the distribution. low is included in the range.
- **high** (*float*) Upper endpoint of the range of the distribution. **high** is included in the range.
- **q** (*float*) A discretization step.

Raises ValueError – If low value is larger than high value, or q value is smaller or equal to 0.

Return type None

low

Lower endpoint of the range of the distribution. low is included in the range.

high

Upper endpoint of the range of the distribution. high is included in the range.

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use FloatDistribution instead.

Methods

single()	Test whether the range of this distribution contains
	just a single value.
to_external_repr(param_value_in_internal_repr)	Convert internal representation of a parameter value
	into external representation.
to_internal_repr(param_value_in_external_repr)	Convert external representation of a parameter value
	into internal representation.

Attributes

	q	Discretization step.
--	---	----------------------

property q: float

Discretization step.

DiscreteUniformDistribution is a subtype of *FloatDistribution*. This property is a proxy for its step attribute.

single()

Test whether the range of this distribution contains just a single value.

Returns True if the range of this distribution contains just a single value, otherwise False.

Return type bool

to_external_repr(param_value_in_internal_repr)

Convert internal representation of a parameter value into external representation.

Parameters param_value_in_internal_repr (float) — Optuna's internal representation of a parameter value.

Returns Optuna's external representation of a parameter value.

Return type Any

to_internal_repr(param_value_in_external_repr)

Convert external representation of a parameter value into internal representation.

Parameters param_value_in_external_repr (*Any*) – Optuna's external representation of a parameter value.

Returns Optuna's internal representation of a parameter value.

Return type float

optuna.distributions.IntUniformDistribution

class optuna.distributions.IntUniformDistribution(low, high, step=1)

A uniform distribution on integers.

This object is instantiated by *suggest_int()*, and passed to *samplers* in general.

Note: If the range [low, high] is not divisible by step, high will be replaced with the maximum of $k \times \text{step} + \text{low} < \text{high}$, where k is an integer.

low

Lower endpoint of the range of the distribution. low is included in the range.

high

Upper endpoint of the range of the distribution. high is included in the range.

step

A step for spacing between values.

Raises ValueError – If low value is larger than high value, or step value is smaller or equal to 0.

Parameters

- low(int)-
- high (int) -
- step (int) -

Return type None

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use IntDistribution instead.

Methods

single()	Test whether the range of this distribution contains
	just a single value.
to_external_repr(param_value_in_internal_repr)	Convert internal representation of a parameter value
	into external representation.
to_internal_repr(param_value_in_external_repr)	Convert external representation of a parameter value
	into internal representation.

single()

Test whether the range of this distribution contains just a single value.

Returns True if the range of this distribution contains just a single value, otherwise False.

Return type bool

to_external_repr(param_value_in_internal_repr)

Convert internal representation of a parameter value into external representation.

Parameters param_value_in_internal_repr (*float*) – Optuna's internal representation of a parameter value.

Returns Optuna's external representation of a parameter value.

Return type int

to_internal_repr(param_value_in_external_repr)

Convert external representation of a parameter value into internal representation.

Parameters param_value_in_external_repr (*int*) – Optuna's external representation of a parameter value.

Returns Optuna's internal representation of a parameter value.

Return type float

optuna.distributions.IntLogUniformDistribution

class optuna.distributions.**IntLogUniformDistribution**(low, high, step=1)

A uniform distribution on integers in the log domain.

This object is instantiated by suggest_int(), and passed to samplers in general.

low

Lower endpoint of the range of the distribution. low is included in the range.

high

Upper endpoint of the range of the distribution. high is included in the range.

step

A step for spacing between values.

Warning: Deprecated in v2.0.0. step argument will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change.

Samplers and other components in Optuna relying on this distribution will ignore this value and assume that step is always 1. User-defined samplers may continue to use other values besides 1 during the deprecation.

Raises ValueError – If low value is larger than high value, or low value is smaller than 1.

Parameters

- low (int) -
- high (int) -
- step (int) -

Return type None

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use IntDistribution instead.

Methods

single()	Test whether the range of this distribution contains
	just a single value.
to_external_repr(param_value_in_internal_repr)	Convert internal representation of a parameter value
	into external representation.
to_internal_repr(param_value_in_external_repr)	Convert external representation of a parameter value
	into internal representation.

single()

Test whether the range of this distribution contains just a single value.

Returns True if the range of this distribution contains just a single value, otherwise False.

Return type bool

to_external_repr(param_value_in_internal_repr)

Convert internal representation of a parameter value into external representation.

Parameters param_value_in_internal_repr (*float*) – Optuna's internal representation of a parameter value.

Returns Optuna's external representation of a parameter value.

Return type int

to_internal_repr(param value in external repr)

Convert external representation of a parameter value into internal representation.

Parameters param_value_in_external_repr (*int*) – Optuna's external representation of a parameter value.

Returns Optuna's internal representation of a parameter value.

Return type float

optuna.distributions.CategoricalDistribution

class optuna.distributions.CategoricalDistribution(choices)

A categorical distribution.

This object is instantiated by suggest_categorical(), and passed to samplers in general.

Parameters choices (Sequence[Union[None, bool, int, float, str]]) - Parameter value candidates.

Return type None

Note: Not all types are guaranteed to be compatible with all storages. It is recommended to restrict the types of the choices to None, bool, int, float and str.

choices

Parameter value candidates.

Raises ValueError – If choices do not contain any elements.

Parameters choices (Sequence[Union[None, bool, int, float, str]]) -

Return type None

Methods

single()	Test whether the range of this distribution contains
	just a single value.
to_external_repr(param_value_in_internal_repr)	Convert internal representation of a parameter value
	into external representation.
to_internal_repr(param_value_in_external_repr)	Convert external representation of a parameter value
	into internal representation.

single()

Test whether the range of this distribution contains just a single value.

Returns True if the range of this distribution contains just a single value, otherwise False.

Return type bool

to_external_repr(param_value_in_internal_repr)

Convert internal representation of a parameter value into external representation.

Parameters param_value_in_internal_repr (*float*) – Optuna's internal representation of a parameter value.

Returns Optuna's external representation of a parameter value.

Return type *Union*[None, bool, int, float, str]

```
to_internal_repr(param_value_in_external_repr)
```

Convert external representation of a parameter value into internal representation.

Parameters param_value_in_external_repr (Union[None, bool, int, float, str]) — Optuna's external representation of a parameter value.

Returns Optuna's internal representation of a parameter value.

Return type float

optuna.distributions.distribution to json

```
optuna.distributions.distribution_to_json(dist)
```

Serialize a distribution to JSON format.

Parameters dist (optuna.distributions.BaseDistribution) — A distribution to be serialized.

Returns A JSON string of a given distribution.

Return type str

optuna.distributions.json_to_distribution

```
optuna.distributions.json_to_distribution(json_str)
```

Deserialize a distribution in JSON format.

Parameters json_str (str) – A JSON-serialized distribution.

Returns A description.

Raises ValueError – If the unknown class is specified.

Return type optuna.distributions.BaseDistribution

optuna.distributions.check distribution compatibility

```
optuna.distributions.check_distribution_compatibility(dist_old, dist_new)
```

A function to check compatibility of two distributions.

Note that this method is not supposed to be called by library users.

Parameters

- dist_old (optuna.distributions.BaseDistribution) A distribution previously recorded in storage.
- **dist_new** (optuna.distributions.BaseDistribution) A distribution newly added to storage.

Raises ValueError — If different distribution kinds are set to dist_old and dist_new, or dist_old.choices doesn't match dist_new.choices for *CategoricalDistribution*.

Return type None

6.3.4 optuna.exceptions

The *exceptions* module defines Optuna-specific exceptions deriving from a base *OptunaError* class. Of special importance for library users is the *TrialPruned* exception to be raised if *optuna.trial.Trial.should_prune()* returns **True** for a trial that should be pruned.

optuna.exceptions.OptunaError	Base class for Optuna specific errors.
optuna.exceptions.TrialPruned	Exception for pruned trials.
optuna.exceptions.CLIUsageError	Exception for CLI.
optuna.exceptions.StorageInternalError	Exception for storage operation.
optuna.exceptions.DuplicatedStudyError	Exception for a duplicated study name.

optuna.exceptions.OptunaError

```
exception optuna.exceptions.OptunaError
```

Base class for Optuna specific errors.

optuna.exceptions.TrialPruned

exception optuna.exceptions.TrialPruned

Exception for pruned trials.

This error tells a trainer that the current *Trial* was pruned. It is supposed to be raised after *optuna.trial*. *Trial.should_prune()* as shown in the following example.

See also:

optuna. TrialPruned is an alias of optuna. exceptions. TrialPruned.

Example

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split

import optuna

X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)

def objective(trial):
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
    clf = SGDClassifier(alpha=alpha)
    n_train_iter = 100

for step in range(n_train_iter):
    clf.partial_fit(X_train, y_train, classes=classes)
```

(continues on next page)

(continued from previous page)

```
intermediate_value = clf.score(X_valid, y_valid)
    trial.report(intermediate_value, step)

if trial.should_prune():
    raise optuna.TrialPruned()

return clf.score(X_valid, y_valid)

study = optuna.create_study(direction="maximize")
study.optimize(objective, n_trials=20)
```

optuna.exceptions.CLIUsageError

exception optuna.exceptions.CLIUsageError

Exception for CLI.

CLI raises this exception when it receives invalid configuration.

optuna.exceptions.StorageInternalError

exception optuna.exceptions.StorageInternalError

Exception for storage operation.

This error is raised when an operation failed in backend DB of storage.

optuna.exceptions.DuplicatedStudyError

exception optuna.exceptions.DuplicatedStudyError

Exception for a duplicated study name.

This error is raised when a specified study name already exists in the storage.

6.3.5 optuna.importance

The *importance* module provides functionality for evaluating hyperparameter importances based on completed trials in a given study. The utility function <code>get_param_importances()</code> takes a <code>Study</code> and optional evaluator as two of its inputs. The evaluator must derive from <code>BaseImportanceEvaluator</code>, and is initialized as a <code>FanovaImportanceEvaluator</code> by default when not passed in. Users implementing custom evaluators should refer to either <code>FanovaImportanceEvaluator</code> or <code>MeanDecreaseImpurityImportanceEvaluator</code> as a guide, paying close attention to the format of the return value from the <code>Evaluator</code>'s <code>evaluate()</code> function.

optuna.importance.get_param_importances	Evaluate parameter importances based on completed tri-
	als in the given study.
optuna.importance.	fANOVA importance evaluator.
FanovaImportanceEvaluator	
optuna.importance.	Mean Decrease Impurity (MDI) parameter importance
${\tt MeanDecreaseImpurityImportanceEvaluator}$	evaluator.

optuna.importance.get param importances

optuna.importance.get_param_importances(study, *, evaluator=None, params=None, target=None)

Evaluate parameter importances based on completed trials in the given study.

The parameter importances are returned as a dictionary where the keys consist of parameter names and their values importances. The importances are represented by floating point numbers that sum to 1.0 over the entire dictionary. The higher the value, the more important. The returned dictionary is of type collections.OrderedDict and is ordered by its values in a descending order.

If params is None, all parameter that are present in all of the completed trials are assessed. This implies that conditional parameters will be excluded from the evaluation. To assess the importances of conditional parameters, a list of parameter names can be specified via params. If specified, only completed trials that contain all of the parameters will be considered. If no such trials are found, an error will be raised.

If the given study does not contain completed trials, an error will be raised.

Note: If params is specified as an empty list, an empty dictionary is returned.

See also:

See plot_param_importances() to plot importances.

Parameters

- **study** (optuna.study.study) An optimized study.
- evaluator (Optional [optuna.importance._base.BaseImportanceEvaluator]) An importance evaluator object that specifies which algorithm to base the importance assessment on. Defaults to FanovaImportanceEvaluator.
- params (Optional[List[str]]) A list of names of parameters to assess. If None, all parameters that are present in all of the completed trials are assessed.
- target (Optional [Callable [[optuna.trial._frozen.FrozenTrial], float]])

 A function to specify the value to evaluate importances. If it is None and study is being used for single-objective optimization, the objective values are used.

Note: Specify this argument if study is being used for multi-objective optimization. For example, to get the hyperparameter importance of the first objective, use target=lambda t: t.values[0] for the target parameter.

Returns An collections.OrderedDict where the keys are parameter names and the values are assessed importances.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type *Dict*[str, float]

optuna.importance.FanovalmportanceEvaluator

class optuna.importance.FanovaImportanceEvaluator(*, n_trees=64, max_depth=64, seed=None)

fANOVA importance evaluator.

Implements the fANOVA hyperparameter importance evaluation algorithm in An Efficient Approach for Assessing Hyperparameter Importance.

Given a study, fANOVA fits a random forest regression model that predicts the objective value given a parameter configuration. The more accurate this model is, the more reliable the importances assessed by this class are.

Note: Requires the sklearn Python package.

Note: Pairwise and higher order importances are not supported through this class. They can be computed using _Fanova directly but is not recommended as interfaces may change without prior notice.

Note: The performance of fANOVA depends on the prediction performance of the underlying random forest model. In order to obtain high prediction performance, it is necessary to cover a wide range of the hyperparameter search space. It is recommended to use an exploration-oriented sampler such as *RandomSampler*.

Note: For how to cite the original work, please refer to https://automl.github.io/fanova/cite.html.

Parameters

- **n_trees** (*int*) The number of trees in the forest.
- max_depth (int) The maximum depth of the trees in the forest.
- **seed** (*Optional [int]*) Controls the randomness of the forest. For deterministic behavior, specify a value other than None.

Return type None

Methods

<pre>evaluate(study[, params, target])</pre>	Evaluate parameter importances based on completed
	trials in the given study.

evaluate(study, params=None, *, target=None)

Evaluate parameter importances based on completed trials in the given study.

Note: This method is not meant to be called by library users.

See also:

Please refer to get_param_importances() for how a concrete evaluator should implement this method.

Parameters

- **study** (optuna.study.study) An optimized study.
- params (Optional [List[str]]) A list of names of parameters to assess. If None, all parameters that are present in all of the completed trials are assessed.
- target (Optional[Callable[[optuna.trial._frozen.FrozenTrial], float]]) A function to specify the value to evaluate importances. If it is None and study is being used for single-objective optimization, the objective values are used. Can also be used for other trial attributes, such as the duration, like target=lambda t: t.duration.total_seconds().

Note: Specify this argument if study is being used for multi-objective optimization. For example, to get the hyperparameter importance of the first objective, use target=lambda t: t.values[0] for the target parameter.

Returns An collections.OrderedDict where the keys are parameter names and the values are assessed importances.

Raises ValueError — If target is None and study is being used for multi-objective optimization.

Return type *Dict*[str, float]

optuna.importance.MeanDecreaseImpurityImportanceEvaluator

Mean Decrease Impurity (MDI) parameter importance evaluator.

This evaluator fits a random forest that predicts objective values given hyperparameter configurations. Feature importances are then computed using MDI.

Note: This evaluator requires the sklean Python package and is based on sklearn.ensemble.RandomForestClassifier.feature_importances_.

Parameters

- **n_trees** (*int*) Number of trees in the random forest.
- max_depth (int) The maximum depth of each tree in the random forest.
- **seed** (Optional[int]) Seed for the random forest.

Return type None

Methods

evaluate(study[, params, target])	Evaluate parameter importances based on completed
	trials in the given study.

evaluate(study, params=None, *, target=None)

Evaluate parameter importances based on completed trials in the given study.

Note: This method is not meant to be called by library users.

See also:

Please refer to get_param_importances() for how a concrete evaluator should implement this method.

Parameters

- study (optuna.study.study) An optimized study.
- params (Optional [List[str]]) A list of names of parameters to assess. If None, all parameters that are present in all of the completed trials are assessed.
- target (Optional[Callable[[optuna.trial._frozen.FrozenTrial], float]]) A function to specify the value to evaluate importances. If it is None and study is being used for single-objective optimization, the objective values are used. Can also be used for other trial attributes, such as the duration, like target=lambda t: t.duration.total_seconds().

Note: Specify this argument if study is being used for multi-objective optimization. For example, to get the hyperparameter importance of the first objective, use target=lambda t: t.values[0] for the target parameter.

Returns An collections.OrderedDict where the keys are parameter names and the values are assessed importances.

Raises ValueError — If target is None and study is being used for multi-objective optimization.

Return type *Dict*[str, float]

6.3.6 optuna.integration

The integration module contains classes used to integrate Optuna with external machine learning frameworks.

For most of the ML frameworks supported by Optuna, the corresponding Optuna integration class serves only to implement a callback object and functions, compliant with the framework's specific callback API, to be called with each intermediate step in the model training. The functionality implemented in these callbacks across the different ML frameworks includes:

- (1) Reporting intermediate model scores back to the Optuna trial using optuna.trial.report(),
- (2) According to the results of optuna.trial.Trial.should_prune(), pruning the current model by raising optuna.TrialPruned(), and

(3) Reporting intermediate Optuna data such as the current trial number back to the framework, as done in *MLflowCallback*.

For scikit-learn, an integrated *OptunaSearchCV* estimator is available that combines scikit-learn BaseEstimator functionality with access to a class-level Study object.

AllenNLP

optuna.integration.AllenNLPExecutor	AllenNLP extension to use optuna with Jsonnet config
	file.
optuna.integration.allennlp.	Save JSON config file with environment variables and
dump_best_config	best performing hyperparameters.
optuna.integration.AllenNLPPruningCallback	AllenNLP callback to prune unpromising trials.

optuna.integration.AllenNLPExecutor

AllenNLP extension to use optuna with Jsonnet config file.

See the examples of objective function.

You can also see the tutorial of our AllenNLP integration on AllenNLP Guide.

Note: From Optuna v2.1.0, users have to cast their parameters by using methods in Jsonnet. Call std.parseInt for integer, or std.parseJson for floating point. Please see the example configuration.

Note: In *AllenNLPExecutor*, you can pass parameters to AllenNLP by either defining a search space using Optuna suggest methods or setting environment variables just like AllenNLP CLI. If a value is set in both a search space in Optuna and the environment variables, the executor will use the value specified in the search space in Optuna.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **config_file** (*str*) Config file for AllenNLP. Hyperparameters should be masked with std.extVar. Please refer to the config example.
- **serialization_dir** (*str*) A path which model weights and logs are saved.
- **metrics** (*str*) An evaluation metric. GradientDescrentTrainer.train() of AllenNLP returns a dictionary containing metrics after training. *AllenNLPExecutor* accesses the dictionary by the key metrics you specify and use it as a objective value.
- **force** (*bool*) If True, an executor overwrites the output directory if it exists.
- **file_friendly_logging** (*bool*) If True, tqdm status is printed on separate lines and slows tqdm refresh rate.

• include_package (Optional [Union [str, List[str]]]) – Additional packages to include. For more information, please see AllenNLP documentation.

Methods

run()

Train a model using AllenNLP.

run()

Train a model using AllenNLP.

Return type float

optuna.integration.allennlp.dump_best_config

optuna.integration.allennlp.dump_best_config(input_config_file, output_config_file, study)
Save JSON config file with environment variables and best performing hyperparameters.

Parameters

- input_config_file (str) Input Jsonnet config file used with AllenNLPExecutor.
- **output_config_file** (*str*) Output JSON config file.
- **study** (optuna.study.study) Instance of *Study*. Note that *optimize()* must have been called.

Return type None

optuna.integration.AllenNLPPruningCallback

class optuna.integration.**AllenNLPPruningCallback**(trial=None, monitor=None)

AllenNLP callback to prune unpromising trials.

See the example if you want to add a pruning callback which observes a metric.

You can also see the tutorial of our AllenNLP integration on AllenNLP Guide.

Note: When AllenNLPPruningCallback is instantiated in Python script, trial and monitor are mandatory.

On the other hand, when AllenNLPPruningCallback is used with AllenNLPExecutor, trial and monitor would be None. AllenNLPExecutor sets environment variables for a study name, trial id, monitor, and storage. Then AllenNLPPruningCallback loads them to restore trial and monitor.

Note: Currently, build-in pruners are supported except for *PatientPruner*.

Parameters

- **trial** (Optional [optuna.trial._trial]) A Trial corresponding to the current evaluation of the objective function.
- monitor (Optional[str]) An evaluation metric for pruning, e.g. validation_loss or validation_accuracy.

Methods

<pre>on_epoch(trainer, metrics, epoch[, is_primary])</pre>	Check if a training reaches saturation.
register(*args, **kwargs)	Stub method for <i>TrainerCallback.register</i> .

on_epoch(trainer, metrics, epoch, is_primary=True, **_)

Check if a training reaches saturation.

Parameters

- trainer (GradientDescentTrainer) AllenNLP's trainer
- metrics (Dict[str, Any]) Dictionary of metrics.
- **epoch** (*int*) Number of current epoch.
- **is_primary** (*bool*) A flag for AllenNLP internal.
- _ (Any) -

Return type None

classmethod register(*args, **kwargs)

Stub method for TrainerCallback.register.

This method has the same signature as Registrable.register in AllenNLP.

Parameters

- args (Any) -
- kwargs (Any) -

Return type *Callable*

BoTorch

optuna.integration.BoTorchSampler	A sampler that uses BoTorch, a Bayesian optimization
	library built on top of PyTorch.
optuna.integration.botorch.	Quasi MC-based batch Expected Improvement (qEI).
qei_candidates_func	
optuna.integration.botorch.	Quasi MC-based batch Expected Hypervolume Im-
qehvi_candidates_func	provement (qEHVI).
optuna.integration.botorch.	Quasi MC-based extended ParEGO (qParEGO) for con-
qparego_candidates_func	strained multi-objective optimization.

optuna.integration.BoTorchSampler

class optuna.integration.**BoTorchSampler**(*, candidates_func=None, constraints_func=None, n_startup_trials=10, independent_sampler=None)

A sampler that uses BoTorch, a Bayesian optimization library built on top of PyTorch.

This sampler allows using BoTorch's optimization algorithms from Optuna to suggest parameter configurations. Parameters are transformed to continuous space and passed to BoTorch, and then transformed back to Optuna's representations. Categorical parameters are one-hot encoded.

See also:

See an example how to use the sampler.

See also:

See the BoTorch homepage for details and for how to implement your own candidates_func.

Note: An instance of this sampler *should not be used with different studies* when used with constraints. Instead, a new instance should be created for each new study. The reason for this is that the sampler is stateful keeping all the computed constraints.

Parameters

• candidates_func (Callable[[torch.Tensor, torch.Tensor, Optional[torch. Tensor], torch.Tensor], torch.Tensor]) — An optional function that suggests the next candidates. It must take the training data, the objectives, the constraints, the search space bounds and return the next candidates. The arguments are of type torch.Tensor. The return value must be a torch.Tensor. However, if constraints_func is omitted, constraints will be None. For any constraints that failed to compute, the tensor will contain NaN.

If omitted, it is determined automatically based on the number of objectives. If the number of objectives is one, Quasi MC-based batch Expected Improvement (qEI) is used. If the number of objectives is either two or three, Quasi MC-based batch Expected Hypervolume Improvement (qEHVI) is used. Otherwise, for larger number of objectives, the faster Quasi MC-based extended ParEGO (qParEGO) is used.

The function should assume *maximization* of the objective.

See also:

See optuna.integration.botorch.qei_candidates_func() for an example.

• constraints_func (Optional[Callable[[optuna.trial._frozen. FrozenTrial], Sequence[float]]]) — An optional function that computes the objective constraints. It must take a FrozenTrial and return the constraints. The return value must be a sequence of float s. A value strictly larger than 0 means that a constraint is violated. A value equal to or smaller than 0 is considered feasible.

If omitted, no constraints will be passed to candidates_func nor taken into account during suggestion.

- **n_startup_trials** (*int*) Number of initial trials, that is the number of trials to resort to independent sampling.
- independent_sampler (Optional[optuna.samplers._base.BaseSampler]) An independent sampler to use for the initial trials and for parameters that are conditional.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

<pre>after_trial(study, trial, state, values)</pre>	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **state** (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional [Sequence [float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before $sample_relative()$ method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using $sample_independent()$ method.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.integration.botorch.qei_candidates_func

 $\verb"optuna.integration.botorch.qei_candidates_func(\textit{train}_x, \textit{train_obj}, \textit{train_con}, \textit{bounds})$

Quasi MC-based batch Expected Improvement (qEI).

The default value of candidates_func in BoTorchSampler with single-objective optimization.

Parameters

- train_x (torch.Tensor) Previous parameter configurations. A torch.Tensor of shape (n_trials, n_params). n_trials is the number of already observed trials and n_params is the number of parameters. n_params may be larger than the actual number of parameters if categorical parameters are included in the search space, since these parameters are one-hot encoded. Values are not normalized.
- **train_obj** (*torch.Tensor*) Previously observed objectives. A torch.Tensor of shape (n_trials, n_objectives). n_trials is identical to that of train_x. n_objectives is the number of objectives. Observations are not normalized.
- train_con (Optional[torch.Tensor]) Objective constraints. A torch.Tensor of shape (n_trials, n_constraints). n_trials is identical to that of train_x. n_constraints is the number of constraints. A constraint is violated if strictly larger than 0. If no constraints are involved in the optimization, this argument will be None.
- **bounds** (*torch.Tensor*) Search space bounds. A torch.Tensor of shape (2, n_params). n_params is identical to that of train_x. The first and the second rows correspond to the lower and upper bounds for each parameter respectively.

Returns Next set of candidates. Usually the return value of BoTorch's optimize_acqf.

Return type torch. Tensor

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

optuna.integration.botorch.qehvi candidates func

optuna.integration.botorch.qehvi_candidates_func(train_x, train_obj, train_con, bounds)

Quasi MC-based batch Expected Hypervolume Improvement (qEHVI).

The default value of candidates_func in *BoTorchSampler* with multi-objective optimization when the number of objectives is three or less.

See also:

qei_candidates_func() for argument and return value descriptions.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- train_x (torch.Tensor) -
- train_obj (torch.Tensor) -
- train_con(Optional[torch.Tensor]) -
- bounds (torch. Tensor) -

Return type torch. Tensor

optuna.integration.botorch.qparego candidates func

optuna.integration.botorch.qparego_candidates_func(train_x, train_obj, train_con, bounds)

Quasi MC-based extended ParEGO (qParEGO) for constrained multi-objective optimization.

The default value of candidates_func in *BoTorchSampler* with multi-objective optimization when the number of objectives is larger than three.

See also:

qei_candidates_func() for argument and return value descriptions.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- train_x (torch.Tensor) -
- train_obj (torch.Tensor) -
- train_con (Optional[torch.Tensor]) -
- bounds (torch. Tensor) -

Return type torch. Tensor

Catalyst

optuna.integration.CatalystPruningCallback Catalyst callback to prune unpromising trials.

optuna.integration.CatalystPruningCallback

class optuna.integration.CatalystPruningCallback(*args, **kwargs)

Catalyst callback to prune unpromising trials.

This class is an alias to Catalyst's OptunaPruningCallback.

See the Catalyst's documentation for the detailed description.

Warning: Deprecated in v2.7.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.7.0.

CatBoost

optuna.integration.CatBoostPruningCallback

class optuna.integration.CatBoostPruningCallback(trial, metric, eval_set_index=None)

Callback for catboost to prune unpromising trials.

See the example if you want to add a pruning callback which observes validation accuracy of a CatBoost model.

Note: optuna.TrialPruned cannot be raised in after_iteration() that is called in CatBoost via CatBoostPruningCallback. You must call check_pruned() after training manually unlike other pruning callbacks to raise optuna.TrialPruned.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- metric (str) An evaluation metric for pruning, e.g., Logloss and AUC. Please refer to CatBoost reference for further details.
- eval_set_index (Optional[int]) The index of the target validation dataset. If you set only one eval_set, eval_set_index is None. If you set multiple datasets as eval_set, the index of eval_set must be eval_set_index, e.g., 0 or 1 when eval_set contains two datasets.

Return type None

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Methods

after_iteration(info)	Report an evaluation metric value for Optuna pruning
	after each CatBoost's iteration.
check_pruned()	Raise optuna. TrialPruned manually if the Cat-
	Boost optimization is pruned.

after_iteration(info)

Report an evaluation metric value for Optuna pruning after each CatBoost's iteration.

This method is called by CatBoost.

```
Parameters info (Any) - A SimpleNamespace containing iteraion, validation_name,
  metric_name and history of losses. For example SimpleNamespace(iteration=2,
  metrics={ 'learn': {'Logloss': [0.6, 0.5]}, 'validation':
  {'Logloss': [0.7, 0.6], 'AUC': [0.8, 0.9]} }).
```

Returns A boolean value. If False, CatBoost internally stops the optimization with Optuna's pruning logic without raising *optuna.TrialPruned*. Otherwise, the optimization continues

Return type bool

check_pruned()

Raise optuna. TrialPruned manually if the CatBoost optimization is pruned.

Return type None

Chainer

optuna.integration.ChainerPruningExtension	Chainer extension to prune unpromising trials.
optuna.integration.ChainerMNStudy	A wrapper of <i>Study</i> to incorporate Optuna with Chain-
	erMN.

optuna.integration.ChainerPruningExtension

class optuna.integration.ChainerPruningExtension(trial, observation_key, pruner_trigger)

Chainer extension to prune unpromising trials.

See the example if you want to add a pruning extension which observes validation accuracy of a Chainer Trainer.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **observation_key** (*str*) An evaluation metric for pruning, e.g., main/loss and validation/main/accuracy. Please refer to chainer.Reporter reference for further details.
- pruner_trigger (Union[Tuple[int, str], IntervalTrigger, ManualScheduleTrigger]) A trigger to execute pruning. pruner_trigger is an instance of IntervalTrigger or ManualScheduleTrigger. IntervalTrigger can be specified by a tuple of the interval length and its unit like (1, 'epoch').

Return type None

optuna.integration.ChainerMNStudy

class optuna.integration.ChainerMNStudy(study, comm)

A wrapper of *Study* to incorporate Optuna with ChainerMN.

See also:

ChainerMNStudy provides the same interface as Study. Please refer to optuna.study.Study for further details.

See the example if you want to optimize an objective function that trains neural network written with ChainerMN.

Parameters

- study (optuna.study.study) A Study object.
- **comm** (CommunicatorBase) A ChainerMN communicator.

Return type None

Methods

```
optimize(func[, n_trials, timeout, catch])
Optimize an objective function.
```

optimize(func, n_trials=None, timeout=None, catch=())

Optimize an objective function.

This method provides the same interface as optuna.study.Study.optimize() except the absence of n_jobs argument.

Parameters

```
    func (Callable[[ChainerMNTrial, CommunicatorBase], float]) –
    n_trials (Optional[int]) –
    timeout (Optional[float]) –
    catch (Tuple[Type[Exception], ...]) –
```

Return type None

fast.ai

optuna.integration.FastAIV1PruningCallback	FastAI callback to prune unpromising trials for fastai.
optuna.integration.FastAIV2PruningCallback	FastAI callback to prune unpromising trials for fastai.
optuna.integration.FastAIPruningCallback	alias of optuna.integration.fastaiv2.
	FastAIV2PruningCallback

optuna.integration.FastAIV1PruningCallback

class optuna.integration.FastAIV1PruningCallback(learn, trial, monitor)

FastAI callback to prune unpromising trials for fastai.

Note: This callback is for fastai<2.0.

See the example if you want to add a pruning callback which monitors validation loss of a Learner.

Example

Register a pruning callback to learn.fit and learn.fit_one_cycle.

```
learn.fit(n_epochs, callbacks=[FastAIPruningCallback(learn, trial, "valid_loss")])
learn.fit_one_cycle(
    n_epochs,
    cyc_len,
    max_lr,
    callbacks=[FastAIPruningCallback(learn, trial, "valid_loss")],
)
```

Parameters

- **learn** (*Learner*) fastai.basic train.Learner.
- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- monitor (str) An evaluation metric for pruning, e.g. valid_loss and Accuracy. Please refer to fastai.callbacks.TrackerCallback reference for further details.

Return type None

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

```
on_epoch_end(epoch, **kwargs)
```

optuna.integration.FastAIV2PruningCallback

class optuna.integration.FastAIV2PruningCallback(trial, monitor='valid_loss')

FastAI callback to prune unpromising trials for fastai.

Note: This callback is for fastai>=2.0.

See the example if you want to add a pruning callback which monitors validation loss of a Learner.

Example

Register a pruning callback to learn.fit and learn.fit_one_cycle.

```
learn = cnn_learner(dls, resnet18, metrics=[error_rate])
learn.fit(n_epochs, cbs=[FastAIPruningCallback(trial)]) # Monitor "valid_loss"
learn.fit_one_cycle(
    n_epochs,
    lr_max,
    cbs=[FastAIPruningCallback(trial, monitor="error_rate")], # Monitor "error_rate"
)
```

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **monitor** (*str*) An evaluation metric for pruning, e.g. valid_loss or accuracy. Please refer to fastai.callback.TrackerCallback reference for further details.

Methods

after_epoch()
after_fit()

optuna.integration.FastAlPruningCallback

 $optuna.integration. \textbf{\textit{FastAIPruningCallback}}$

alias of optuna.integration.fastaiv2.FastAIV2PruningCallback

Keras

optuna.integration.KerasPruningCallback

Keras callback to prune unpromising trials.

optuna.integration.KerasPruningCallback

class optuna.integration.KerasPruningCallback(trial, monitor, interval=1)

Keras callback to prune unpromising trials.

See the example if you want to add a pruning callback which observes validation accuracy.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **monitor** (*str*) An evaluation metric for pruning, e.g., val_loss and val_accuracy. Please refer to keras.Callback reference for further details.
- **interval** (*int*) Check if trial should be pruned every n-th epoch. By default interval=1 and pruning is performed after every epoch. Increase interval to run several epochs faster before applying pruning.

Return type None

Warning: Deprecated in v2.1.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.1.0.

Recent Keras release (2.4.0) simply redirects all APIs in the standalone keras package to point to tf.keras. There is now only one Keras: tf.keras. There may be some breaking changes for some workflows by upgrading to keras 2.4.0. Test before upgrading. REF: https://github.com/keras-team/keras/releases/tag/2.4.0. There is an alternative callback function that can be used instead: *TFKerasPruningCallback*

Methods

on_epoch_end(epoch[, logs])

LightGBM

optuna.integration.LightGBMPruningCallback	Callback for LightGBM to prune unpromising trials.
optuna.integration.lightgbm.train	Wrapper of LightGBM Training API to tune hyperpa-
	rameters.
optuna.integration.lightgbm.LightGBMTuner	Hyperparameter tuner for LightGBM.
optuna.integration.lightgbm.	Hyperparameter tuner for LightGBM with cross-
LightGBMTunerCV	validation.

optuna.integration.LightGBMPruningCallback

Callback for LightGBM to prune unpromising trials.

See the example if you want to add a pruning callback which observes accuracy of a LightGBM model.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **metric** (*str*) An evaluation metric for pruning, e.g., binary_error and multi_error. Please refer to LightGBM reference for further details.
- **valid_name** (*str*) The name of the target validation. Validation names are specified by valid_names option of train method. If omitted, valid_0 is used which is the default name of the first validation. Note that this argument will be ignored if you are calling cv method instead of train method.
- **report_interval** (*int*) Check if the trial should report intermediate values for pruning every n-th boosting iteration. By default **report_interval=1** and reporting is performed after every iteration. Note that the pruning itself is performed according to the interval definition of the pruner.

Return type None

optuna.integration.lightgbm.train

optuna.integration.lightgbm.train(*args, **kwargs)

Wrapper of LightGBM Training API to tune hyperparameters.

It tunes important hyperparameters (e.g., min_child_samples and feature_fraction) in a stepwise manner. It is a drop-in replacement for lightgbm.train(). See a simple example of LightGBM Tuner which optimizes the validation log loss of cancer detection.

train() is a wrapper function of *LightGBMTuner*. To use feature in Optuna such as suspended/resumed optimization and/or parallelization, refer to *LightGBMTuner* instead of this function.

Arguments and keyword arguments for lightgbm.train() can be passed.

Parameters

- args (Any) -
- kwargs (Any) -

Return type *Any*

optuna.integration.lightgbm.LightGBMTuner

class optuna.integration.lightgbm.LightGBMTuner(params, train_set, num_boost_round=1000,

valid_sets=None, valid_names=None, fobj=None, feval=None, feature_name='auto', categorical_feature='auto', early_stopping_rounds=None, evals_result=None, verbose_eval='warn', learning_rates=None, keep_training_booster=False, callbacks=None, time_budget=None, sample_size=None, study=None, optuna_callbacks=None, model_dir=None, verbosity=None, show_progress_bar=True, *, optuna_seed=None)

Hyperparameter tuner for LightGBM.

It optimizes the following hyperparameters in a stepwise manner: lambda_11, lambda_12, num_leaves, feature_fraction, bagging_fraction, bagging_freq and min_child_samples.

You can find the details of the algorithm and benchmark results in this blog article by Kohei Ozaki, a Kaggle Grandmaster.

Arguments and keyword arguments for lightgbm.train() can be passed. The arguments that only *LightGBMTuner* has are listed below:

Parameters

- time_budget (Optional[int]) A time budget for parameter tuning in seconds.
- **study** (Optional [optuna.study.study.Study]) A Study instance to store optimization results. The Trial instances in it has the following user attributes: elapsed_secs is the elapsed time since the optimization starts. average_iteration_time is the average time of iteration to train the booster model in the trial. lgbm_params is a JSON-serialized dictionary of LightGBM parameters used in the trial.
- optuna_callbacks (Optional[List[Callable[[optuna.study.study.optuna.trial._frozen.FrozenTrial], None]]])—List of Optuna callback functions that are invoked at the end of each trial. Each function must accept two parameters with the following types in this order: Study and FrozenTrial. Please note that this is not a callbacks argument of lightgbm.train().
- model_dir (Optional[str]) A directory to save boosters. By default, it is set to None and no boosters are saved. Please set shared directory (e.g., directories on NFS) if you want to access get_best_booster() in distributed environments. Otherwise, it may raise ValueError. If the directory does not exist, it will be created. The filenames of the boosters will be {model_dir}/{trial_number}.pkl (e.g., ./boosters/0.pkl).
- **verbosity** (Optional[int]) A verbosity level to change Optuna's logging level. The level is aligned to LightGBM's verbosity.

Warning: Deprecated in v2.0.0. verbosity argument will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change.

Please use *set_verbosity()* instead.

• **show_progress_bar** (*bool*) – Flag to show progress bars or not. To disable progress bar, set this False.

Note: Progress bars will be fragmented by logging messages of LightGBM and Optuna. Please suppress such messages to show the progress bars properly.

• **optuna_seed** (Optional[int]) — **seed** of TPESampler for random number generator that affects sampling for num_leaves, bagging_fraction, bagging_freq, lambda_l1, and lambda_l2.

Note: The deterministic parameter of LightGBM makes training reproducible. Please enable it when you use this argument.

```
params (Dict[str, Any]) -train_set (lgb.Dataset) -
```

- num_boost_round(int)-
- valid_sets (Optional[VALID_SET_TYPE]) -
- valid_names (Optional[Any]) -
- fobj (Optional [Callable [[...], Any]]) -
- feval (Optional [Callable [[...], Any]]) -
- feature_name (str) -
- categorical_feature(str)-
- early_stopping_rounds (Optional[int]) -
- evals_result (Optional[Dict[Any, Any]]) -
- verbose_eval(Optional[Union[bool, int, str]])-
- learning_rates (Optional [List[float]]) -
- keep_training_booster(bool) -
- callbacks (Optional[List[Callable[[...], Any]]]) -
- sample_size (Optional[int]) -

Return type None

Methods

compare_validation_metrics(val_score,	
best_score)	
<pre>get_best_booster()</pre>	Return the best booster.
higher_is_better()	
run()	Perform the hyperparameter-tuning with given pa-
	rameters.
<pre>sample_train_set()</pre>	Make subset of self.train_set Dataset object.
tune_bagging([n_trials])	
<pre>tune_feature_fraction([n_trials])</pre>	
<pre>tune_feature_fraction_stage2([n_trials])</pre>	
tung min data in loaf()	
<pre>tune_min_data_in_leaf()</pre>	
tune_num_leaves([n trials])	
(
<pre>tune_regularization_factors([n_trials])</pre>	

Attributes

best_params	Return parameters of the best booster.
best_score	Return the score of the best booster.

property best_params: Dict[str, Any]

Return parameters of the best booster.

property best_score: float

Return the score of the best booster.

get_best_booster()

Return the best booster.

If the best booster cannot be found, ValueError will be raised. To prevent the errors, please save boosters by specifying the model_dir argument of __init__(), when you resume tuning or you run tuning in parallel.

Return type lightgbm.basic.Booster

run()

Perform the hyperparameter-tuning with given parameters.

Return type None

sample_train_set()

Make subset of self.train_set Dataset object.

Return type None

optuna.integration.lightgbm.LightGBMTunerCV

class optuna.integration.lightgbm.LightGBMTunerCV(params, train_set, num_boost_round=1000,

folds=None, nfold=5, stratified=True, shuffle=True, fobj=None, feval=None, feature_name='auto', categorical_feature='auto', early_stopping_rounds=None, fpreproc=None, verbose_eval=None, show_stdv=True, seed=0, callbacks=None, time_budget=None, sample_size=None, study=None, optuna_callbacks=None, verbosity=None, show_progress_bar=True, model_dir=None, return_cvbooster=False, *, optuna_seed=None)

Hyperparameter tuner for LightGBM with cross-validation.

It employs the same stepwise approach as *LightGBMTuner*. *LightGBMTunerCV* invokes lightgbm.cv() to train and validate boosters while *LightGBMTuner* invokes lightgbm.train(). See a simple example which optimizes the validation log loss of cancer detection.

Arguments and keyword arguments for lightgbm.cv() can be passed except metrics, init_model and eval_train_metric. The arguments that only *LightGBMTunerCV* has are listed below:

Parameters

- time_budget (Optional [int]) A time budget for parameter tuning in seconds.
- **study** (Optional [optuna.study.study.Study]) A Study instance to store optimization results. The Trial instances in it has the following user attributes: elapsed_secs is the elapsed time since the optimization starts. average_iteration_time is the average time of iteration to train the booster model in the trial. lgbm_params is a JSON-serialized dictionary of LightGBM parameters used in the trial.
- optuna_callbacks (Optional[List[Callable[[optuna.study.study.optuna.trial._frozen.FrozenTrial], None]]])—List of Optuna callback functions that are invoked at the end of each trial. Each function must accept two parameters with the following types in this order: Study and FrozenTrial. Please note that this is not a callbacks argument of lightgbm.train().
- model_dir (Optional[str]) A directory to save boosters. By default, it is set to None and no boosters are saved. Please set shared directory (e.g., directories on NFS) if you want to access get_best_booster() in distributed environments. Otherwise, it may raise ValueError. If the directory does not exist, it will be created. The filenames of the boosters will be {model_dir}/{trial_number}.pkl (e.g., ./boosters/0.pkl).
- **verbosity** (*Optional[int]*) A verbosity level to change Optuna's logging level. The level is aligned to LightGBM's verbosity .

Warning: Deprecated in v2.0.0. verbosity argument will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change.

Please use set_verbosity() instead.

• **show_progress_bar** (*bool*) – Flag to show progress bars or not. To disable progress bar, set this False.

Note: Progress bars will be fragmented by logging messages of LightGBM and Optuna. Please suppress such messages to show the progress bars properly.

- return_cvbooster (bool) Flag to enable get_best_booster().
- optuna_seed(Optional[int]) seed of TPESampler for random number generator that affects sampling for num_leaves, bagging_fraction, bagging_freq, lambda_l1, and lambda_l2.

Note: The deterministic parameter of LightGBM makes training reproducible. Please enable it when you use this argument.

```
• params (Dict[str, Any]) -
• train_set (lgb.Dataset) -

    num_boost_round(int) -

    folds

                 (Optional[Union[Generator[Tuple[int, int], None, None],
  Iterator[Tuple[int, int]], BaseCrossValidator]]) -
• nfold (int) -
• stratified (bool) -
• shuffle (bool) -
• fobj (Optional [Callable [[...], Any]]) -
• feval (Optional [Callable [[...], Any]]) -
• feature_name (str) -
• categorical_feature(str)-
• early_stopping_rounds (Optional[int]) -
• fpreproc (Optional [Callable [[...], Any]]) -
• verbose_eval (Optional [Union [bool, int]]) -
• show_stdv (bool) -
• seed (int) -
• callbacks (Optional[List[Callable[[...], Any]]]) -
• sample_size (Optional[int]) -
```

6.3. API Reference 109

Return type None

Methods

compare_validation_metrics(val_score,	
best_score)	
<pre>get_best_booster()</pre>	Return the best cybooster.
higher_is_better()	
run()	Perform the hyperparameter-tuning with given parameters.
<pre>sample_train_set()</pre>	Make subset of <i>self.train_set</i> Dataset object.
tune_bagging([n_trials])	
<pre>tune_feature_fraction([n_trials])</pre>	
<pre>tune_feature_fraction_stage2([n_trials])</pre>	
<pre>tune_min_data_in_leaf()</pre>	
<pre>tune_num_leaves([n_trials])</pre>	
<pre>tune_regularization_factors([n_trials])</pre>	

Attributes

best_params	Return parameters of the best booster.
best_score	Return the score of the best booster.

property best_params: Dict[str, Any]

Return parameters of the best booster.

property best_score: float

Return the score of the best booster.

get_best_booster()

Return the best cvbooster.

If the best booster cannot be found, ValueError will be raised. To prevent the errors, please save boosters by specifying both of the model_dir and the return_cvbooster arguments of __init__(), when you resume tuning or you run tuning in parallel.

Return type lightgbm.engine.CVBooster

run()

Perform the hyperparameter-tuning with given parameters.

Return type None

sample_train_set()

Make subset of self.train_set Dataset object.

Return type None

MLflow

```
optuna.integration.MLflowCallback
```

Callback to track Optuna trials with MLflow.

optuna.integration.MLflowCallback

Callback to track Optuna trials with MLflow.

This callback adds relevant information that is tracked by Optuna to MLflow.

Example

Add MLflow callback to Optuna optimization.

```
import optuna
from optuna.integration.mlflow import MLflowCallback

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

mlflc = MLflowCallback(
    tracking_uri=YOUR_TRACKING_URI,
    metric_name="my metric score",
)

study = optuna.create_study(study_name="my_study")
study.optimize(objective, n_trials=10, callbacks=[mlflc])
```

Add additional logging to MLflow

```
import optuna
import mlflow
from optuna.integration.mlflow import MLflowCallback

mlflc = MLflowCallback(
    tracking_uri=YOUR_TRACKING_URI,
    metric_name="my metric score",
)

@mlflc.track_in_mlflow()
def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    mlflow.log_param("power", 2)
    mlflow.log_metric("base of metric", x - 2)
```

(continues on next page)

(continued from previous page)

```
return (x - 2) ** 2

study = optuna.create_study(study_name="my_other_study")
study.optimize(objective, n_trials=10, callbacks=[mlflc])
```

Parameters

- **tracking_uri** (Optional[str]) The URI of the MLflow tracking server.
 - Please refer to mlflow.set_tracking_uri for more details.
- metric_name (Union[str, Sequence[str]]) Name assigned to optimized metric. In case of multi-objective optimization, list of names can be passed. Those names will be assigned to metrics in the order returned by objective function. If single name is provided, or this argument is left to default value, it will be broadcasted to each objective with a number suffix in order returned by objective function e.g. two objectives and default metric name will be logged as value_0 and value_1.
- create_experiment (bool) When True, new MLflow experiment will be created for each optimization run, named after the Optuna study. Setting this argument to False lets user run optimization under existing experiment, set via mlflow.set_experiment, by passing experiment_id as one of mlflow_kwargs or under default MLflow experiment, when no additional arguments are passed. Note that this argument must be set to False when using Optuna with this callback within Databricks Notebook.
- mlflow_kwargs (Optional[Dict[str, Any]]) Set of arguments passed when initializing MLflow run. Please refer to MLflow API documentation for more details.
- tag_study_user_attrs (bool) Flag indicating whether or not to add the study's user attrs to the mlflow trial as tags. Please note that when this flag is set, key value pairs in user_attrs will supersede existing tags.
- tag_trial_user_attrs (bool) Flag indicating whether or not to add the trial's user attrs to the mlflow trial as tags. Please note that when both trial and study user attributes are logged, the latter will supersede the former in case of a collison.

Return type None

Note: nest_trials argument added in v2.3.0 is a part of mlflow_kwargs since v3.0.0. Anyone using nest_trials=True should migrate to mlflow_kwargs={"nested": True} to avoid raising TypeError.

Raises

- ValueError If there are missing or extra metric names in multi-objective optimization.
- **TypeError** When metric names are not passed as sequence.

Parameters

- tracking_uri (Optional[str]) -
- metric_name (Union[str, Sequence[str]]) -
- create_experiment (bool) -
- mlflow_kwargs (Optional[Dict[str, Any]]) -

- tag_study_user_attrs(bool) -
- tag_trial_user_attrs(bool) -

Return type None

Note: Added in v1.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v1.4.0.

Methods

track_in_mlflow()	Decorator for using MLflow logging in the objective
	function.

track_in_mlflow()

Decorator for using MLflow logging in the objective function.

This decorator enables the extension of MLflow logging provided by the callback.

All information logged in the decorated objective function will be added to the MLflow run for the trial created by the callback.

Returns Objective function with tracking to MLflow enabled.

Return type ObjectiveFuncType

Note: Added in v2.9.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.9.0.

Weights & Biases

optuna.integration.	Callback to track Optuna trials with Weights & Biases.
WeightsAndBiasesCallback	

optuna.integration.WeightsAndBiasesCallback

class optuna.integration.WeightsAndBiasesCallback(metric_name='value', wandb_kwargs=None)

Callback to track Optuna trials with Weights & Biases.

This callback enables tracking of Optuna study in Weights & Biases. The study is tracked as a single experiment run, where all suggested hyperparameters and optimized metrics are logged and plotted as a function of optimizer steps.

Note: User needs to be logged in to Weights & Biases before using this callback in online mode. For more information, please refer to wandb setup.

Note: Users who want to run multiple Optuna studies within the same process should call wandb.finish() between subsequent calls to study.optimize(). Calling wandb.finish() is not necessary if you are running one Optuna study per process.

Note: To ensure correct trial order in Weights & Biases, this callback should only be used with study. optimize(n_jobs=1).

Example

Add Weights & Biases callback to Optuna optimization.

```
import optuna
from optuna.integration.wandb import WeightsAndBiasesCallback

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

wandb_kwargs = {"project": "my-project"}
wandbc = WeightsAndBiasesCallback(wandb_kwargs=wandb_kwargs)

study = optuna.create_study(study_name="my_study")
study.optimize(objective, n_trials=10, callbacks=[wandbc])
```

Parameters

- metric_name (Union[str, Sequence[str]]) Name assigned to optimized metric. In case of multi-objective optimization, list of names can be passed. Those names will be assigned to metrics in the order returned by objective function. If single name is provided, or this argument is left to default value, it will be broadcasted to each objective with a number suffix in order returned by objective function e.g. two objectives and default metric name will be logged as value_0 and value_1.
- wandb_kwargs (Optional[Dict[str, Any]]) Set of arguments passed when initializing Weights & Biases run. Please refer to Weights & Biases API documentation for more details.

Raises

- ValueError If there are missing or extra metric names in multi-objective optimization.
- **TypeError** When metric names are not passed as sequence.

Return type None

Note: Added in v2.9.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.9.0.

MXNet

optuna.integration.MXNetPruningCallback

MXNet callback to prune unpromising trials.

optuna.integration.MXNetPruningCallback

class optuna.integration.MXNetPruningCallback(trial, eval_metric)

MXNet callback to prune unpromising trials.

See the example if you want to add a pruning callback which observes accuracy.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **eval_metric** (*str*) An evaluation metric name for pruning, e.g., cross-entropy and accuracy. If using default metrics like mxnet.metrics.Accuracy, use it's default metric name. For custom metrics, use the metric_name provided to constructor. Please refer to mxnet.metrics reference for further details.

Return type None

pycma

optuna.integration.PyCmaSampler	A Sampler using cma library as the backend.
optuna.integration.CmaEsSampler	Wrapper class of PyCmaSampler for backward compat-
	ibility.

optuna.integration.PyCmaSampler

A Sampler using cma library as the backend.

Example

Optimize a simple quadratic function by using *PyCmaSampler*.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -1, 1)
    y = trial.suggest_int("y", -1, 1)
    return x**2 + y

sampler = optuna.integration.PyCmaSampler()
```

(continues on next page)

(continued from previous page)

```
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=20)
```

Note that parallel execution of trials may affect the optimization performance of CMA-ES, especially if the number of trials running in parallel exceeds the population size.

Note: CmaEsSampler is deprecated and renamed to PyCmaSampler in v2.0.0. Please use PyCmaSampler instead of CmaEsSampler.

Parameters

- **x0** (Optional[Dict[str, Any]]) A dictionary of an initial parameter values for CMA-ES. By default, the mean of low and high for each distribution is used. Please refer to cma.CMAEvolutionStrategy for further details of **x0**.
- **sigma0** (Optional[float]) Initial standard deviation of CMA-ES. By default, sigma0 is set to min_range / 6, where min_range denotes the minimum range of the distributions in the search space. If distribution is categorical, min_range is len(choices) 1. Please refer to cma.CMAEvolutionStrategy for further details of sigma0.
- cma_stds (Optional[Dict[str, float]]) A dictionary of multipliers of sigma0 for each parameters. The default value is 1.0. Please refer to cma.CMAEvolutionStrategy for further details of cma_stds.
- **seed** (Optional[int]) A random seed for CMA-ES.
- cma_opts (Optional[Dict[str, Any]]) Options passed to the constructor of cma.CMAEvolutionStrategy class.

Note that BoundaryHandler, bounds, CMA_stds and seed arguments in cma_opts will be ignored because it is added by <code>PyCmaSampler</code> automatically.

- **n_startup_trials** (*int*) The independent sampling is used instead of the CMA-ES algorithm until the given number of trials finish in the same study.
- independent_sampler (Optional [optuna.samplers._base.BaseSampler]) A BaseSampler instance that is used for independent sampling. The parameters not contained in the relative search space are sampled by this sampler. The search space for PyCmaSampler is determined by intersection_search_space().

If None is specified, RandomSampler is used as the default.

See also:

optuna.samplers module provides built-in independent samplers such as RandomSampler and TPESampler.

• warn_independent_sampling (bool) – If this is True, a warning message is emitted when the value of a parameter is sampled by using an independent sampler.

Note that the parameters of the first trial in a study are always sampled via an independent sampler, so no warning messages are emitted in this case.

Return type None

Methods

<pre>after_trial(study, trial, state, values)</pre>	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **state** (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional [Sequence [float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before $sample_relative()$ method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using $sample_independent()$ method.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type float

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- trial (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, float]

optuna.integration.CmaEsSampler

Wrapper class of PyCmaSampler for backward compatibility.

Warning: Deprecated in v2.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.0.0.

This class is renamed to PyCmaSampler.

Methods

after_trial(study, trial, state, values)	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

Parameters

- x0 (Optional[Dict[str, Any]]) -
- **sigma0** (Optional[float]) -
- cma_stds(Optional[Dict[str, float]])-
- seed (Optional[int]) -
- cma_opts(Optional[Dict[str, Any]]) -
- n_startup_trials(int)-
- independent_sampler (Optional[optuna.samplers._base.BaseSampler]) -
- warn_independent_sampling(bool) -

Return type None

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- state (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional[Sequence[float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

• study (optuna.study.study) - Target study object.

- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type float

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, float]

PyTorch

optuna.integration.	PyTorch Ignite handler to prune unpromising trials.
PyTorchIgnitePruningHandler	
optuna.integration.	PyTorch Lightning callback to prune unpromising trials.
PyTorchLightningPruningCallback	
optuna.integration.TorchDistributedTrial	A wrapper of Trial to incorporate Optuna with Py-
	Torch distributed.

optuna.integration.PyTorchlgnitePruningHandler

class optuna.integration.PyTorchIgnitePruningHandler(trial, metric, trainer)

PyTorch Ignite handler to prune unpromising trials.

See the example if you want to add a pruning handler which observes validation accuracy.

Parameters

• **trial** (optuna.trial._trial.Trial) – A *Trial* corresponding to the current evaluation of the objective function.

- **metric** (*str*) A name of metric for pruning, e.g., accuracy and loss.
- **trainer** (*Engine*) A trainer engine of PyTorch Ignite. Please refer to ignite.engine. Engine reference for further details.

Return type None

optuna.integration.PyTorchLightningPruningCallback

class optuna.integration.PyTorchLightningPruningCallback(trial, monitor)

PyTorch Lightning callback to prune unpromising trials.

See the example if you want to add a pruning callback which observes accuracy.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- monitor (str) An evaluation metric for pruning, e.g., val_loss or val_acc. The metrics are obtained from the returned dictionaries from e.g. pytorch_lightning. LightningModule.training_step or pytorch_lightning.LightningModule.validation_epoch_end and the names thus depend on how this dictionary is formatted.

Return type None

Note: For the distributed data parallel training, the version of PyTorchLightning needs to be higher than or equal to v1.5.0. In addition, *Study* should be instantiated with RDB storage.

Methods

```
on_fit_end(trainer, pl_module)

on_init_start(trainer)

on_validation_end(trainer, pl_module)
```

optuna.integration.TorchDistributedTrial

class optuna.integration.TorchDistributedTrial(trial, device=None)

A wrapper of *Trial* to incorporate Optuna with PyTorch distributed.

See also:

TorchDistributedTrial provides the same interface as Trial. Please refer to optuna.trial.Trial for further details.

See the example if you want to optimize an objective function that trains neural network written with PyTorch distributed data parallel.

Parameters

- **trial** (*Optional* [optuna.trial._trial.Trial]) A *Trial* object or None. Please set trial object in rank-0 node and set None in the other rank node.
- **device** (Optional[torch.device]) A torch.device to communicate with the other nodes. Please set a CUDA device assigned to the current node if you use "nccl" as torch.distributed backend.

Return type None

Note: The methods of *TorchDistributedTrial* are expected to be called by all workers at once. They invoke synchronous data transmission to share processing results and synchronize timing.

Note: Added in v2.6.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.6.0.

Methods

```
report(value, step)

set_system_attr(key, value)

set_user_attr(key, value)

should_prune()

suggest_categorical(name, choices)

suggest_discrete_uniform(name, low, high, q)


suggest_float(name, low, high, *[, step, log])

suggest_int(name, low, high[, step, log])

suggest_loguniform(name, low, high)

suggest_uniform(name, low, high)
```

Attributes



suggest_discrete_uniform(name, low, high, q)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

- name (str) -
- low (float) -
- high (float) -
- q(float)-

Return type float

suggest_loguniform(name, low, high)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

- name (str) -
- low (float) -
- high (float) -

Return type float

suggest_uniform(name, low, high)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

- name (str) -
- low (float) -
- high (float) -

Return type float

scikit-learn

optuna.integration.OptunaSearchCV

Hyperparameter search with cross-validation.

optuna.integration.OptunaSearchCV

Hyperparameter search with cross-validation.

Parameters

- **estimator** (*BaseEstimator*) Object to use to fit the data. This is assumed to implement the scikit-learn estimator interface. Either this needs to provide score, or scoring must be passed.
- param_distributions (Mapping[str, optuna.distributions. BaseDistribution]) Dictionary where keys are parameters and values are distributions. Distributions are assumed to implement the optuna distribution interface.
- **cv** (Optional [Union [BaseCrossValidator, int]]) Cross-validation strategy. Possible inputs for cv are:
 - integer to specify the number of folds in a CV splitter,
 - a CV splitter,
 - an iterable yielding (train, validation) splits as arrays of indices.

For integer, if estimator is a classifier and y is either binary or multiclass, sklearn.model_selection.StratifiedKFold is used. otherwise, sklearn.model_selection.KFold is used.

• **enable_pruning** (*bool*) – If True, pruning is performed in the case where the underlying estimator supports partial_fit.

- error_score (Union[numbers.Number, float, str]) Value to assign to the score if an error occurs in fitting. If 'raise', the error is raised. If numeric, sklearn.exceptions. FitFailedWarning is raised. This does not affect the refit step, which will always raise the error.
- max_iter(int) Maximum number of epochs. This is only used if the underlying estimator supports partial_fit.
- n_jobs (int) Number of threading based parallel jobs. -1 means using the number is set to CPU count.

Note: n_jobs allows parallelization using threading and may suffer from Python's GIL. It is recommended to use *process-based parallelization* if func is CPU bound.

- n_trials (int) Number of trials. If None, there is no limitation on the number of trials. If timeout is also set to None, the study continues to create trials until it receives a termination signal such as Ctrl+C or SIGTERM. This trades off runtime vs quality of the solution.
- random_state (Optional[Union[int, numpy.random.mtrand.RandomState]]) Seed of the pseudo random number generator. If int, this is the seed used by the random number generator. If numpy.random.RandomState object, this is the random number generator. If None, the global random state from numpy.random is used.
- **refit** (bool) If True, refit the estimator with the best found hyperparameters. The refitted estimator is made available at the best_estimator_ attribute and permits using predict directly.
- return_train_score (bool) If True, training scores will be included. Computing training scores is used to get insights on how different hyperparameter settings impact the overfitting/underfitting trade-off. However computing training scores can be computationally expensive and is not strictly required to select the hyperparameters that yield the best generalization performance.
- **scoring** (Optional [Union [Callable [[...], float], str]]) String or callable to evaluate the predictions on the validation data. If None, score on the estimator is used.
- **study** (*Optional* [optuna.study.study]) Study corresponds to the optimization task. If None, a new study is created.
- **subsample** (*Union[float*, *int]*) Proportion of samples that are used during hyperparameter search.
 - If int, then draw subsample samples.
 - If float, then draw subsample * X.shape[0] samples.
- timeout (Optional [float]) Time limit in seconds for the search of appropriate models. If None, the study is executed without time limitation. If n_trials is also set to None, the study continues to create trials until it receives a termination signal such as Ctrl+C or SIGTERM. This trades off runtime vs quality of the solution.
- **verbose** (*int*) Verbosity level. The higher, the more messages.

Return type None

best_estimator_

Estimator that was chosen by the search. This is present only if refit is set to True.

n_splits_

Number of cross-validation splits.

refit_time_

Time for refitting the best estimator. This is present only if refit is set to True.

sample_indices_

Indices of samples that are used during hyperparameter search.

scorer_

Scorer function.

study_

Actual study.

Examples

```
import optuna
from sklearn.datasets import load_iris
from sklearn.svm import SVC

clf = SVC(gamma="auto")
param_distributions = {
    "C": optuna.distributions.FloatDistribution(1e-10, 1e10, log=True)
}
optuna_search = optuna.integration.OptunaSearchCV(clf, param_distributions)
X, y = load_iris(return_X_y=True)
optuna_search.fit(X, y)
y_pred = optuna_search.predict(X)
```

Note: By following the scikit-learn convention for scorers, the direction of optimization is maximize. See https://scikit-learn.org/stable/modules/model_evaluation.html. For the minimization problem, please multiply -1.

Note: Added in v0.17.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v0.17.0.

Methods

<pre>fit(X[, y, groups])</pre>	Run fit with all sets of parameters.
<pre>get_params([deep])</pre>	Get parameters for this estimator.
score(X[, y])	Return the score on the given data.
set_params(**params)	Set the parameters of this estimator.

Attributes

Trial number which corresponds to the best candidate
parameter setting.
Parameters of the best trial in the <i>Study</i> .
Mean cross-validated score of the best estimator.
Best trial in the <i>Study</i> .
Class labels.
Call decision_function on the best estimator.
Call inverse_transform on the best estimator.
Actual number of trials.
Call predict on the best estimator.
Call predict_log_proba on the best estimator.
Call predict_proba on the best estimator.
Call score_samples on the best estimator.
Call set_user_attr on the Study.
Call transform on the best estimator.
All trials in the <i>Study</i> .
Call trials_dataframe on the Study.
User attributes in the <i>Study</i> .

property best_index_: int

Trial number which corresponds to the best candidate parameter setting.

Retuned value is equivant to optuna_search.best_trial_.number.

property best_params_: Dict[str, Any]

Parameters of the best trial in the *Study*.

property best_score_: float

Mean cross-validated score of the best estimator.

property best_trial_: optuna.trial._frozen.FrozenTrial

Best trial in the Study.

property classes_: Union[List[float], numpy.ndarray, pandas.core.series.Series]
 Class labels.

property decision_function: Callable[[...], Union[List[float], numpy.ndarray,
pandas.core.series.Series, List[List[float]], pandas.core.frame.DataFrame,
scipy.sparse._base.spmatrix]]

Call decision_function on the best estimator.

This is available only if the underlying estimator supports decision_function and refit is set to True.

fit(*X*, *y*=*None*, *groups*=*None*, **fit_params)

Run fit with all sets of parameters.

Parameters

- X (Union[List[List[float]], numpy.ndarray, pandas.core.frame. DataFrame, scipy.sparse._base.spmatrix]) Training data.
- y (Optional[Union[List[float], numpy.ndarray, pandas.core.series. Series, List[List[float]], pandas.core.frame.DataFrame, scipy. sparse._base.spmatrix]]) Target variable.

- groups (Optional[Union[List[float], numpy.ndarray, pandas.core. series.Series]]) Group labels for the samples used while splitting the dataset into train/validation set.
- **fit_params Parameters passed to fit on the estimator.
- fit_params (Any) -

Returns Return self.

Return type self

```
get_params(deep=True)
```

Get parameters for this estimator.

Parameters deep (*bool*, *default=True*) – If True, will return the parameters for this estimator and contained subobjects that are estimators.

Returns params – Parameter names mapped to their values.

Return type dict

```
property inverse_transform: Callable[[...], Union[List[List[float]], numpy.ndarray,
pandas.core.frame.DataFrame, scipy.sparse._base.spmatrix]]
```

Call inverse_transform on the best estimator.

This is available only if the underlying estimator supports inverse_transform and refit is set to True.

```
property n_trials_: int
```

Actual number of trials.

```
property predict: Callable[[...], Union[List[float], numpy.ndarray,
pandas.core.series.Series, List[List[float]], pandas.core.frame.DataFrame,
scipy.sparse._base.spmatrix]]
```

Call predict on the best estimator.

This is available only if the underlying estimator supports predict and refit is set to True.

```
property predict_log_proba: Callable[[...], Union[List[List[float]], numpy.ndarray,
pandas.core.frame.DataFrame, scipy.sparse._base.spmatrix]]
```

Call predict_log_proba on the best estimator.

This is available only if the underlying estimator supports predict_log_proba and refit is set to True.

```
property predict_proba: Callable[[...], Union[List[List[float]], numpy.ndarray,
pandas.core.frame.DataFrame, scipy.sparse._base.spmatrix]]
```

Call predict_proba on the best estimator.

This is available only if the underlying estimator supports predict_proba and refit is set to True.

```
score(X, y=None)
```

Return the score on the given data.

Parameters

- X (Union[List[List[float]], numpy.ndarray, pandas.core.frame. DataFrame, scipy.sparse._base.spmatrix]) Data.
- y (Optional[Union[List[float], numpy.ndarray, pandas.core.series. Series, List[List[float]], pandas.core.frame.DataFrame, scipy. sparse._base.spmatrix]]) Target variable.

Returns Scaler score.

```
Return type score
```

```
property score_samples: Callable[[...], Union[List[float], numpy.ndarray,
pandas.core.series.Series]]
```

Call score_samples on the best estimator.

This is available only if the underlying estimator supports score_samples and refit is set to True.

```
set_params(**params)
```

Set the parameters of this estimator.

The method works on simple estimators as well as on nested objects (such as Pipeline). The latter have parameters of the form <component>__<parameter> so that it's possible to update each component of a nested object.

Parameters **params (dict) – Estimator parameters.

Returns self – Estimator instance.

Return type estimator instance

```
property set_user_attr: Callable[[...], None]
```

Call set_user_attr on the Study.

```
property transform: Callable[[...], Union[List[List[float]], numpy.ndarray,
pandas.core.frame.DataFrame, scipy.sparse._base.spmatrix]]
```

Call transform on the best estimator.

This is available only if the underlying estimator supports transform and refit is set to True.

```
property trials_: List[optuna.trial._frozen.FrozenTrial]
```

All trials in the Study.

```
property trials_dataframe: Callable[[...], pandas.core.frame.DataFrame]
```

Call trials_dataframe on the Study.

```
property user_attrs_: Dict[str, Any]
```

User attributes in the *Study*.

scikit-optimize

optuna.integration.SkoptSampler

Sampler using Scikit-Optimize as the backend.

optuna.integration.SkoptSampler

Sampler using Scikit-Optimize as the backend.

Example

Optimize a simple quadratic function by using *SkoptSampler*.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    y = trial.suggest_int("y", 0, 10)
    return x**2 + y

sampler = optuna.integration.SkoptSampler()
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)
```

Parameters

• independent_sampler (Optional [optuna.samplers._base.BaseSampler]) - A BaseSampler instance that is used for independent sampling. The parameters not contained in the relative search space are sampled by this sampler. The search space for SkoptSampler is determined by intersection_search_space().

If None is specified, RandomSampler is used as the default.

See also:

optuna.samplers module provides built-in independent samplers such as RandomSampler and TPESampler.

• warn_independent_sampling (bool) – If this is True, a warning message is emitted when the value of a parameter is sampled by using an independent sampler.

Note that the parameters of the first trial in a study are always sampled via an independent sampler, so no warning messages are emitted in this case.

• **skopt_kwargs** (*Optional[Dict[str, Any]]*) – Keyword arguments passed to the constructor of skopt. Optimizer class.

Note that dimensions argument in skopt_kwargs will be ignored because it is added by *SkoptSampler* automatically.

- n_startup_trials (int) The independent sampling is used until the given number of trials finish in the same study.
- **consider_pruned_trials** (*bool*) If this is True, the PRUNED trials are considered for sampling.

Note: Added in v2.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.0.0.

Note: As the number of trials n increases, each sampling takes longer and longer on a scale of $O(n^3)$. And, if this is True, the number of trials will increase. So, it is suggested to set this flag False when each evaluation of the objective function is relatively faster than each

sampling. On the other hand, it is suggested to set this flag True when each evaluation of the objective function is relatively slower than each sampling.

Return type None

Methods

after_trial(study, trial, state, values)	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
sample_relative(study, trial, search_space)	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- state (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional[Sequence[float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to *intersection_search_space()* as an implementation of *infer_relative_search_space()*.

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

• **search_space** (Dict[str, optuna.distributions.BaseDistribution]) - The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

skorch

optuna.integration.SkorchPruningCallback	Skorch callback to prune unpromising trials.

optuna.integration.SkorchPruningCallback

class optuna.integration.SkorchPruningCallback(trial, monitor)

Skorch callback to prune unpromising trials.

New in version 2.1.0.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **monitor** (*str*) An evaluation metric for pruning, e.g. val_loss or val_acc. The metrics are obtained from the returned dictionaries, i.e., net.histroy. The names thus depend on how this dictionary is formatted.

Return type None

Methods

on_epoch_end(net, **kwargs)

TensorFlow

optuna.integration.TensorBoardCallback	Callback to track Optuna trials with TensorBoard.
optuna.integration.TensorFlowPruningHook	TensorFlow SessionRunHook to prune unpromising tri-
	als.
optuna.integration.TFKerasPruningCallback	tf.keras callback to prune unpromising trials.

optuna.integration.TensorBoardCallback

class optuna.integration.TensorBoardCallback(dirname, metric_name)

Callback to track Optuna trials with TensorBoard.

This callback adds relevant information that is tracked by Optuna to TensorBoard.

See the example.

Parameters

- **dirname** (*str*) Directory to store TensorBoard logs.
- **metric_name** (*str*) Name of the metric. Since the metric itself is just a number, *metric_name* can be used to give it a name. So you know later if it was roc-auc or accuracy.

Return type None

Note: Added in v2.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.0.0.

optuna.integration.TensorFlowPruningHook

class optuna.integration.TensorFlowPruningHook(trial, estimator, metric, run_every_steps)

TensorFlow SessionRunHook to prune unpromising trials.

See the example if you want to add a pruning hook to TensorFlow's estimator.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- estimator (tf.estimator.Estimator) An estimator which you will use.
- **metric** (*str*) An evaluation metric for pruning, e.g., accuracy and loss.
- **run_every_steps** (*int*) An interval to watch the summary file.

Return type None

Methods

after_run(run_context, run_values)		
before_run(run_context)		
begin()		

optuna.integration.TFKerasPruningCallback

class optuna.integration.TFKerasPruningCallback(trial, monitor)

tf.keras callback to prune unpromising trials.

This callback is intend to be compatible for TensorFlow v1 and v2, but only tested with TensorFlow v2.

See the example if you want to add a pruning callback which observes the validation accuracy.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **monitor** (*str*) An evaluation metric for pruning, e.g., val_loss or val_acc.

Return type None

Methods

on_epoch_end(epoch[, logs])

XGBoost

optuna.integration.XGBoostPruningCallback Callback for XGBoost to prune unpromising trials.

optuna.integration.XGBoostPruningCallback

class optuna.integration.XGBoostPruningCallback(trial, observation_key)

Callback for XGBoost to prune unpromising trials.

See the example if you want to add a pruning callback which observes validation accuracy of a XGBoost model.

Parameters

- **trial** (optuna.trial._trial.Trial) A *Trial* corresponding to the current evaluation of the objective function.
- **observation_key** (*str*) An evaluation metric for pruning, e.g., validation-error and validation-merror. When using the Scikit-Learn API, the index number of eval_set must be included in the observation_key, e.g., validation_0-error and validation_0-merror. Please refer to eval_metric in XGBoost reference for further details.

Return type None

6.3.7 optuna.logging

The *logging* module implements logging using the Python logging package. Library users may be especially interested in setting verbosity levels using $set_verbosity()$ to one of optuna.logging.CRITICAL (aka optuna.logging.FATAL), optuna.logging.ERROR, optuna.logging.WARNING (aka optuna.logging.WARN), optuna.logging.INFO, or optuna.logging.DEBUG.

optuna.logging.get_verbosity	Return the current level for the Optuna's root logger.
optuna.logging.set_verbosity	Set the level for the Optuna's root logger.
optuna.logging.disable_default_handler	Disable the default handler of the Optuna's root logger.
optuna.logging.enable_default_handler	Enable the default handler of the Optuna's root logger.
optuna.logging.disable_propagation	Disable propagation of the library log outputs.
optuna.logging.enable_propagation	Enable propagation of the library log outputs.

optuna.logging.get_verbosity

```
optuna.logging.get_verbosity()
```

Return the current level for the Optuna's root logger.

Example

Get the default verbosity level.

```
import optuna

# The default verbosity level of Optuna is `optuna.logging.INFO`.
print(optuna.logging.get_verbosity())
# 20
print(optuna.logging.INFO)
# 20

# There are logs of the INFO level.
study = optuna.create_study()
study.optimize(objective, n_trials=5)
# [I 2021-10-31 05:35:17,232] A new study created ...
# [I 2021-10-31 05:35:17,238] Trial 0 finished with value: ...
# [I 2021-10-31 05:35:17,245] Trial 1 finished with value: ...
# ...
```

Returns Logging level, e.g., optuna.logging.DEBUG and optuna.logging.INFO.

Return type int

Note: Optuna has following logging levels:

- optuna.logging.CRITICAL, optuna.logging.FATAL
- optuna.logging.ERROR
- optuna.logging.WARNING, optuna.logging.WARN
- optuna.logging.INFO

• optuna.logging.DEBUG

optuna.logging.set verbosity

```
\verb"optuna.logging.set_verbosity" (\textit{verbosity})
```

Set the level for the Optuna's root logger.

Example

Set the logging level optuna.logging.WARNING.

```
import optuna

# There are INFO level logs.
study = optuna.create_study()
study.optimize(objective, n_trials=10)

# [I 2021-10-31 02:59:35,088] Trial 0 finished with value: 16.0 ...

# [I 2021-10-31 02:59:35,091] Trial 1 finished with value: 1.0 ...

# [I 2021-10-31 02:59:35,096] Trial 2 finished with value: 1.0 ...

# Setting the logging level WARNING, the INFO logs are suppressed.
optuna.logging.set_verbosity(optuna.logging.WARNING)
study.optimize(objective, n_trials=10)
```

Parameters verbosity (int) — Logging level, e.g., optuna.logging.DEBUG and optuna. logging.INFO.

Return type None

Note: Optuna has following logging levels:

- optuna.logging.CRITICAL, optuna.logging.FATAL
- optuna.logging.ERROR
- optuna.logging.WARNING,optuna.logging.WARN
- optuna.logging.INFO
- optuna.logging.DEBUG

optuna.logging.disable default handler

```
optuna.logging.disable_default_handler()
```

Disable the default handler of the Optuna's root logger.

Example

Stop and then resume logging to sys.stderr.

```
import optuna
study = optuna.create_study()

# There are no logs in sys.stderr.
optuna.logging.disable_default_handler()
study.optimize(objective, n_trials=10)

# There are logs in sys.stderr.
optuna.logging.enable_default_handler()
study.optimize(objective, n_trials=10)
# [I 2020-02-23 17:00:54,314] Trial 10 finished with value: ...
# [I 2020-02-23 17:00:54,356] Trial 11 finished with value: ...
# ...
```

Return type None

optuna.logging.enable_default_handler

```
optuna.logging.enable_default_handler()
```

Enable the default handler of the Optuna's root logger.

Please refer to the example shown in disable_default_handler().

Return type None

optuna.logging.disable propagation

```
optuna.logging.disable_propagation()
```

Disable propagation of the library log outputs.

Note that log propagation is disabled by default. You only need to use this function to stop log propagation when you use enable_propagation().

Example

Stop propagating logs to the root logger on the second optimize call.

```
import optuna
import logging

optuna.logging.disable_default_handler() # Disable the default handler.
logger = logging.getLogger()

logger.setLevel(logging.INFO) # Setup the root logger.
logger.addHandler(logging.FileHandler("foo.log", mode="w"))

optuna.logging.enable_propagation() # Propagate logs to the root logger.
```

(continues on next page)

(continued from previous page)

```
study = optuna.create_study()
logger.info("Logs from first optimize call") # The logs are saved in the logs file.
study.optimize(objective, n_trials=10)

optuna.logging.disable_propagation() # Stop propogating logs to the root logger.

logger.info("Logs from second optimize call")
# The new logs for second optimize call are not saved.
study.optimize(objective, n_trials=10)

with open("foo.log") as f:
    assert f.readline().startswith("A new study created")
    assert f.readline() = "Logs from first optimize call\n"
    # Check for logs after second optimize call.
    assert f.read().split("Logs from second optimize call\n")[-1] == ""
```

Return type None

optuna.logging.enable_propagation

```
optuna.logging.enable_propagation()
```

Enable propagation of the library log outputs.

Please disable the Optuna's default handler to prevent double logging if the root logger has been configured.

Example

Propagate all log output to the root logger in order to save them to the file.

```
import optuna
import logging

logger = logging.getLogger()

logger.setLevel(logging.INFO)  # Setup the root logger.
logger.addHandler(logging.FileHandler("foo.log", mode="w"))

optuna.logging.enable_propagation()  # Propagate logs to the root logger.
optuna.logging.disable_default_handler()  # Stop showing logs in sys.stderr.

study = optuna.create_study()

logger.info("Start optimization.")
study.optimize(objective, n_trials=10)

with open("foo.log") as f:
    assert f.readline().startswith("A new study created")
    assert f.readline() == "Start optimization.\n"
```

Return type None

6.3.8 optuna.multi_objective

This module is deprecated, with former functionality moved to optuna.samplers, optuna.study, optuna.trial and optuna.visualization.

optuna.multi objective.samplers

optuna.multi_objective.samplers.	Base class for multi-objective samplers.
BaseMultiObjectiveSampler	
optuna.multi_objective.samplers.	Multi-objective sampler using the NSGA-II algorithm.
NSGAIIMultiObjectiveSampler	
optuna.multi_objective.samplers.	Multi-objective sampler using random sampling.
RandomMultiObjectiveSampler	
optuna.multi_objective.samplers.	Multi-objective sampler using the MOTPE algorithm.
MOTPEMultiObjectiveSampler	

optuna.multi_objective.samplers.BaseMultiObjectiveSampler

class optuna.multi_objective.samplers.BaseMultiObjectiveSampler(*args, **kwargs)

Base class for multi-objective samplers.

The abstract methods of this class are the same as ones defined by <code>BaseSampler</code> except for taking multi-objective versions of study and trial instances as the arguments.

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

abstract infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- **study**(optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *MultiObjectiveStudy* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

abstract sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by sample_relative() method. This method is suitable for sampling algorithms that do not use the relationship between parameters such as random sampling.

Parameters

- **study** (optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

abstract sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use the relationship between parameters.

Parameters

- **study**(optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.multi objective.samplers.NSGAIIMultiObjectiveSampler

Multi-objective sampler using the NSGA-II algorithm.

NSGA-II stands for "Nondominated Sorting Genetic Algorithm II", which is a well known, fast and elitist multiobjective genetic algorithm.

For further information about NSGA-II, please refer to the following paper:

• A fast and elitist multiobjective genetic algorithm: NSGA-II

Parameters

- **population_size** (*int*) Number of individuals (trials) in a generation.
- mutation_prob (Optional[float]) Probability of mutating each parameter when creating a new individual. If None is specified, the value 1.0 / len(parent_trial. params) is used where parent_trial is the parent trial of the target individual.
- **crossover_prob** (*float*) Probability that a crossover (parameters swapping between parents) will occur when creating a new individual.
- **swapping_prob** (*float*) Probability of swapping each parameter of the parents during crossover.
- **seed** (*Optional* [*int*]) Seed for random number generator.

Return type None

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- **study** (optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *MultiObjectiveStudy* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by sample_relative() method. This method is suitable for sampling algorithms that do not use the relationship between parameters such as random sampling.

Parameters

- **study** (optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- trial (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.
- param_name (str) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use the relationship between parameters.

Parameters

- **study** (optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.multi_objective.samplers.RandomMultiObjectiveSampler

```
class optuna.multi_objective.samplers.RandomMultiObjectiveSampler(seed=None)
```

Multi-objective sampler using random sampling.

This sampler is based on *independent sampling*. See also *BaseMultiObjectiveSampler* for more details of 'independent sampling'.

Example

```
import optuna
from optuna.multi_objective.samplers import RandomMultiObjectiveSampler

def objective(trial):
    x = trial.suggest_float("x", -5, 5)
    y = trial.suggest_float("y", -5, 5)
    return x**2, y + 10

study = optuna.multi_objective.create_study(
    ["minimize", "minimize"], sampler=RandomMultiObjectiveSampler()
)
study.optimize(objective, n_trials=10)
```

Args: seed: Seed for random number generator.

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

Parameters seed (Optional[int]) -

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- **study** (optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *MultiObjectiveStudy* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by sample_relative() method. This method is suitable for sampling algorithms that do not use the relationship between parameters such as random sampling.

Parameters

- **study**(optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.

- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type *Any*

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use the relationship between parameters.

Parameters

- **study**(optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- trial (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.multi objective.samplers.MOTPEMultiObjectiveSampler

class optuna.multi_objective.samplers.MOTPEMultiObjectiveSampler(consider_prior=True,

prior_weight=1.0, consider_magic_clip=True, consider_endpoints=True, n_startup_trials=10, n_ehvi_candidates=24, gamma=<function default_gamma>, weights_above=<function _default_weights_above>, seed=None)

Multi-objective sampler using the MOTPE algorithm.

This sampler is a multiobjective version of *TPESampler*.

For further information about MOTPE algorithm, please refer to the following paper:

• Multiobjective tree-structured parzen estimator for computationally expensive optimization problems

Parameters

- **consider_prior** (*bool*) Enhance the stability of Parzen estimator by imposing a Gaussian prior when True. The prior is only effective if the sampling distribution is either *FloatDistribution*, or *IntDistribution*.
- **prior_weight** (*float*) The weight of the prior. This argument is used in *FloatDistribution*, *IntDistribution*, and *CategoricalDistribution*.

- consider_magic_clip (bool) Enable a heuristic to limit the smallest variances of Gaussians used in the Parzen estimator.
- **consider_endpoints** (*bool*) Take endpoints of domains into account when calculating variances of Gaussians in Parzen estimator. See the original paper for details on the heuristics to calculate the variances.
- n_startup_trials (int) The random sampling is used instead of the MOTPE algorithm until the given number of trials finish in the same study. 11 * number of variables 1 is recommended in the original paper.
- n_ehvi_candidates (int) Number of candidate samples used to calculate the expected hypervolume improvement.
- gamma (Callable[[int], int]) A function that takes the number of finished trials and returns the number of trials to form a density function for samples with low grains. See the original paper for more details.
- weights_above (Callable[[int], numpy.ndarray]) A function that takes the number of finished trials and returns a weight for them. As default, weights are automatically calculated by the MOTPE's default strategy.
- **seed** (Optional[int]) Seed for random number generator.

Return type None

Note: Initialization with Latin hypercube sampling may improve optimization performance. However, the current implementation only supports initialization with random sampling.

Example

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- **study**(optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *MultiObjectiveStudy* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param name, param distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by sample_relative() method. This method is suitable for sampling algorithms that do not use the relationship between parameters such as random sampling.

Parameters

• **study**(optuna.multi_objective.study.MultiObjectiveStudy) - Target study object.

- trial (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use the relationship between parameters.

Parameters

- **study** (optuna.multi_objective.study.MultiObjectiveStudy) Target study object.
- **trial** (optuna.multi_objective.trial.FrozenMultiObjectiveTrial) Target trial object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.multi objective.study

optuna.multi_objective.study.	A study corresponds to a multi-objective optimization
MultiObjectiveStudy	task, i.e., a set of trials.
optuna.multi_objective.study.create_study	Create a new MultiObjectiveStudy.
optuna.multi_objective.study.load_study	Load the existing MultiObjectiveStudy that has the
	specified name.

optuna.multi objective.study.MultiObjectiveStudy

class optuna.multi_objective.study.MultiObjectiveStudy(study)

A study corresponds to a multi-objective optimization task, i.e., a set of trials.

This object provides interfaces to run a new Trial, access trials' history, set/get user-defined attributes of the study itself.

Note that the direct use of this constructor is not recommended. To create and load a study, please refer to the documentation of <code>create_study()</code> and <code>load_study()</code> respectively.

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

<pre>enqueue_trial(params)</pre>	Enqueue a trial with given parameter values.
<pre>get_pareto_front_trials()</pre>	Return trials located at the pareto front in the study.
<pre>get_trials([deepcopy, states])</pre>	Return all trials in the study.
<pre>optimize(objective[, timeout, n_trials,])</pre>	Optimize an objective function.
set_system_attr(key, value)	Set a system attribute to the study.
set_user_attr(key, value)	Set a user attribute to the study.

Attributes

directions	Return the optimization direction list.
n_objectives	Return the number of objectives.
sampler	Return the sampler.
system_attrs	Return system attributes.
trials	Return all trials in the study.
user_attrs	Return user attributes.

Parameters study (optuna.study.study.Study) -

property directions: List[optuna.study._study_direction.StudyDirection]

Return the optimization direction list.

Returns A list that contains the optimization direction for each objective value.

enqueue_trial(params)

Enqueue a trial with given parameter values.

You can fix the next sampling parameters which will be evaluated in your objective function.

Please refer to the documentation of optuna.study.Study.enqueue_trial() for further details.

Parameters params (*Dict[str, Any]*) – Parameter values to pass your objective function.

Return type None

get_pareto_front_trials()

Return trials located at the pareto front in the study.

A trial is located at the pareto front if there are no trials that dominate the trial. It's called that a trial t0 dominates another trial t1 if $all(v0 \le v1)$ for v0, v1 in zip(t0.values, t1.values) and any(v0 < v1) for v0, v1 in zip(t0.values, t1.values) are held.

Returns A list of *FrozenMultiObjectiveTrial* objects.

Return type List[optuna.multi_objective.trial.FrozenMultiObjectiveTrial]

get_trials(deepcopy=True, states=None)

Return all trials in the study.

The returned trials are ordered by trial number.

Parameters

• **deepcopy** (*bool*) – Flag to control whether to apply **copy**. **deepcopy**() to the trials. Note that if you set the flag to False, you shouldn't mutate any fields of the returned trial. Otherwise the internal state of the study may corrupt and unexpected behavior may happen.

• **states** (Optional[Container[optuna.trial._state.TrialState]]) - Trial states to filter on. If None, include all states.

Returns A list of FrozenMultiObjectiveTrial objects.

Return type List[optuna.multi_objective.trial.FrozenMultiObjectiveTrial]

```
property n_objectives: int
```

Return the number of objectives.

Returns Number of objectives.

Optimize an objective function.

This method is the same as *optuna.study.Study.optimize()* except for taking an objective function that returns multi-objective values as the argument.

Please refer to the documentation of optuna.study.Study.optimize() for further details.

Example

```
import optuna

def objective(trial):
    # Binh and Korn function.
    x = trial.suggest_float("x", 0, 5)
    y = trial.suggest_float("y", 0, 3)

    v0 = 4 * x**2 + 4 * y**2
    v1 = (x - 5) ** 2 + (y - 5) ** 2
    return v0, v1

study = optuna.multi_objective.create_study(["minimize", "minimize"])
study.optimize(objective, n_trials=3)
```

Parameters

Return type None

property sampler: optuna.multi_objective.samplers._base.BaseMultiObjectiveSampler

Return the sampler.

Returns A BaseMultiObjectiveSampler object.

```
set_system_attr(key, value)
```

Set a system attribute to the study.

Note that Optuna internally uses this method to save system messages. Please use set_user_attr() to set users' attributes.

Parameters

- **key** (*str*) A key string of the attribute.
- value (Any) A value of the attribute. The value should be JSON serializable.

Return type None

```
set_user_attr(key, value)
```

Set a user attribute to the study.

Parameters

- **key** (*str*) A key string of the attribute.
- value (Any) A value of the attribute. The value should be JSON serializable.

Return type None

```
property system_attrs: Dict[str, Any]
```

Return system attributes.

Returns A dictionary containing all system attributes.

```
property trials: List[optuna.multi_objective.trial.FrozenMultiObjectiveTrial]
```

Return all trials in the study.

The returned trials are ordered by trial number.

This is a short form of self.get_trials(deepcopy=True, states=None).

Returns A list of *FrozenMultiObjectiveTrial* objects.

```
property user_attrs: Dict[str, Any]
```

Return user attributes.

Returns A dictionary containing all user attributes.

optuna.multi objective.study.create study

```
optuna.multi_objective.study.create_study(directions, study_name=None, storage=None, sampler=None, load_if_exists=False)
```

Create a new MultiObjectiveStudy.

Example

```
import optuna

def objective(trial):
    # Binh and Korn function.
    x = trial.suggest_float("x", 0, 5)
    y = trial.suggest_float("y", 0, 3)

    v0 = 4 * x**2 + 4 * y**2
    v1 = (x - 5) ** 2 + (y - 5) ** 2
    return v0, v1

study = optuna.multi_objective.create_study(["minimize", "minimize"])
study.optimize(objective, n_trials=3)
```

Parameters

- directions (List[str]) Optimization direction for each objective value. Set minimize
 for minimization and maximize for maximization.
- **study_name** (*Optional[str]*) Study's name. If this argument is set to None, a unique name is generated automatically.
- **storage** (Optional[Union[str, optuna.storages._base.BaseStorage]]) Database URL. If this argument is set to None, in-memory storage is used, and the Study will not be persistent.

Note:

When a database URL is passed, Optuna internally uses SQLAlchemy to handle the database. Please refer to SQLAlchemy's document for further details. If you want to specify non-default options to SQLAlchemy Engine, you can instantiate *RDBStorage* with your desired options and pass it to the storage argument instead of a URL.

- sampler (Optional[optuna.multi_objective.samplers._base. BaseMultiObjectiveSampler]) A sampler object that implements background algorithm for value suggestion. If None is specified, NSGAIIMultiObjectiveSampler is used as the default. See also samplers.
- **load_if_exists** (bool) Flag to control the behavior to handle a conflict of study names. In the case where a study named study_name already exists in the storage, a <code>DuplicatedStudyError</code> is raised if <code>load_if_exists</code> is set to False. Otherwise, the creation of the study is skipped, and the existing one is returned.

Returns A MultiObjectiveStudy object.

Return type optuna.multi objective.study.MultiObjectiveStudy

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

optuna.multi_objective.study.load_study

```
optuna.multi_objective.study.load_study(study_name, storage, sampler=None)

Load the existing MultiObjectiveStudy that has the specified name.
```

Example

```
import optuna
def objective(trial):
    # Binh and Korn function.
   x = trial.suggest_float("x", 0, 5)
   y = trial.suggest_float("y", 0, 3)
    v0 = 4 * x**2 + 4 * y**2
   v1 = (x - 5) ** 2 + (y - 5) ** 2
    return v0, v1
study = optuna.multi_objective.create_study(
    directions=["minimize", "minimize"],
    study_name="my_study",
    storage="sqlite:///example.db",
study.optimize(objective, n_trials=3)
loaded_study = optuna.multi_objective.study.load_study(
    study_name="my_study", storage="sqlite:///example.db"
assert len(loaded_study.trials) == len(study.trials)
```

Parameters

- **study_name** (*str*) Study's name. Each study has a unique name as an identifier.
- **storage** (*Union[str, optuna.storages._base.BaseStorage]*) Database URL such as **sqlite:**///example.db. Please see also the documentation of *create_study()* for further details.
- sampler (Optional[optuna.multi_objective.samplers._base. BaseMultiObjectiveSampler]) A sampler object that implements background algorithm for value suggestion. If None is specified, RandomMultiObjectiveSampler is used as the default. See also samplers.

Returns A MultiObjectiveStudy object.

Return type optuna.multi_objective.study.MultiObjectiveStudy

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

optuna.multi objective.trial

optuna.multi_objective.trial. MultiObjectiveTrial	A trial is a process of evaluating an objective function.
optuna.multi_objective.trial. FrozenMultiObjectiveTrial	Status and results of a MultiObjectiveTrial.

optuna.multi_objective.trial.MultiObjectiveTrial

class optuna.multi_objective.trial.MultiObjectiveTrial(trial)

A trial is a process of evaluating an objective function.

This object is passed to an objective function and provides interfaces to get parameter suggestion, manage the trial's state, and set/get user-defined attributes of the trial.

Note that the direct use of this constructor is not recommended. This object is seamlessly instantiated and passed to the objective function behind the <code>optuna.multi_objective.study.MultiObjectiveStudy.optimize()</code> method; hence library users do not care about instantiation of this object.

Parameters trial (optuna.trial._trial.Trial) - A Trial object.

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

report(values, step)	Report intermediate objective function values for a given step.
set_system_attr(key, value)	Set system attributes to the trial.
set_user_attr(key, value)	Set user attributes to the trial.
<pre>suggest_categorical(name, choices)</pre>	Suggest a value for the categorical parameter.
<pre>suggest_discrete_uniform(name, low, high, q)</pre>	Suggest a value for the discrete parameter.
<pre>suggest_float(name, low, high, *[, step, log])</pre>	Suggest a value for the floating point parameter.
suggest_int(name, low, high[, step, log])	Suggest a value for the integer parameter.
<pre>suggest_loguniform(name, low, high)</pre>	Suggest a value for the continuous parameter.
<pre>suggest_uniform(name, low, high)</pre>	Suggest a value for the continuous parameter.

Attributes

datetime_start	Return start datetime.
distributions	Return distributions of parameters to be optimized.
number	Return trial's number which is consecutive and
	unique in a study.
params	Return parameters to be optimized.
system_attrs	Return system attributes.
user_attrs	Return user attributes.

property datetime_start: Optional[datetime.datetime]

Return start datetime.

Returns Datetime where the *Trial* started.

property distributions: Dict[str, optuna.distributions.BaseDistribution]

Return distributions of parameters to be optimized.

Returns A dictionary containing all distributions.

property number: int

Return trial's number which is consecutive and unique in a study.

Returns A trial number.

property params: Dict[str, Any]

Return parameters to be optimized.

Returns A dictionary containing all parameters.

report(values, step)

Report intermediate objective function values for a given step.

The reported values are used by the pruners to determine whether this trial should be pruned.

See also:

Please refer to BasePruner.

Note: The reported values are converted to float type by applying float() function internally. Thus, it accepts all float-like types (e.g., numpy.float32). If the conversion fails, a TypeError is raised.

Parameters

- values (Sequence[float]) Intermediate objective function values for a given step.
- **step** (*int*) Step of the trial (e.g., Epoch of neural network training).

Return type None

set_system_attr(key, value)

Set system attributes to the trial.

Please refer to the documentation of optuna.trial.Trial.set_system_attr() for further details.

Parameters

- key (str) -
- value (Any) -

Return type None

set_user_attr(key, value)

Set user attributes to the trial.

Please refer to the documentation of optuna.trial.Trial.set_user_attr() for further details.

Parameters

- key (str) -
- value (*Any*) –

Return type None

suggest_categorical(name, choices)

Suggest a value for the categorical parameter.

Please refer to the documentation of optuna.trial.Trial.suggest_categorical() for further details.

Parameters

- name (str) -
- choices (Sequence [Union [None, bool, int, float, str]]) -

Return type *Union*[None, bool, int, float, str]

$suggest_discrete_uniform(name, low, high, q)$

Suggest a value for the discrete parameter.

Please refer to the documentation of *optuna.trial.Trial.suggest_discrete_uniform()* for further details.

Parameters

- name (str) -
- low (float) -
- high (float) -
- q(float)-

Return type float

```
suggest_float(name, low, high, *, step=None, log=False)
```

Suggest a value for the floating point parameter.

Please refer to the documentation of optuna.trial.Trial.suggest_float() for further details.

Parameters

- name (str) -
- low (float) -
- high (float) -
- step(Union[None, float]) -
- log (bool) -

Return type float

suggest_int(name, low, high, step=1, log=False)

Suggest a value for the integer parameter.

Please refer to the documentation of <code>optuna.trial.Trial.suggest_int()</code> for further details.

Parameters

- name (*str*) –
- low (int) -
- high (int) -
- step (int) -

```
• log (bool) – Return type int
```

suggest_loguniform(name, low, high)

Suggest a value for the continuous parameter.

Please refer to the documentation of optuna.trial.Trial.suggest_loguniform() for further details.

Parameters

- name (str) -
- low (float) -
- high (float) -

Return type float

suggest_uniform(name, low, high)

Suggest a value for the continuous parameter.

Please refer to the documentation of optuna.trial.Trial.suggest_uniform() for further details.

Parameters

- name (str) -
- low (float) -
- high (float) -

Return type float

```
property system_attrs: Dict[str, Any]
```

Return system attributes.

Returns A dictionary containing all system attributes.

```
property user_attrs: Dict[str, Any]
```

Return user attributes.

Returns A dictionary containing all user attributes.

optuna.multi_objective.trial.FrozenMultiObjectiveTrial

```
class optuna.multi_objective.trial.FrozenMultiObjectiveTrial(n_objectives, trial)
```

Status and results of a MultiObjectiveTrial.

Parameters

- n_objectives (int) -
- trial (optuna.trial._frozen.FrozenTrial) -

number

Unique and consecutive number of *MultiObjectiveTrial* for each *MultiObjectiveStudy*. Note that this field uses zero-based numbering.

state

TrialState of the MultiObjectiveTrial.

values

Objective values of the MultiObjectiveTrial.

datetime_start

Datetime where the MultiObjectiveTrial started.

datetime_complete

Datetime where the MultiObjectiveTrial finished.

params

Dictionary that contains suggested parameters.

distributions

Dictionary that contains the distributions of params.

user_attrs

Dictionary that contains the attributes of the MultiObjectiveTrial set with optuna. multi_objective.trial.MultiObjectiveTrial.set_user_attr().

intermediate_values

Intermediate objective values set with optuna.multi_objective.trial.MultiObjectiveTrial.report().

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Attributes

datetime_complete
datetime_start
distributions
last_step
number
params
state
system_attrs
user_attrs

optuna.multi_objective.visualization

Note: *optuna.multi_objective.visualization* module uses plotly to create figures, but JupyterLab cannot render them by default. Please follow this installation guide to show figures in JupyterLab.

```
optuna.multi_objective.visualization. Plot the pareto front of a study. plot_pareto_front
```

optuna.multi_objective.visualization.plot_pareto_front

```
optuna.multi_objective.visualization.plot_pareto_front(study, names=None, include_dominated_trials=False, axis_order=None)
```

Plot the pareto front of a study.

Example

The following code snippet shows how to plot the pareto front of a study.

```
def objective(trial):
    x = trial.suggest_float("x", 0, 5)
    y = trial.suggest_float("y", 0, 3)

    v0 = 4 * x ** 2 + 4 * y ** 2
    v1 = (x - 5) ** 2 + (y - 5) ** 2
    return v0, v1

study = optuna.multi_objective.create_study(["minimize", "minimize"])
study.optimize(objective, n_trials=50)

fig = optuna.multi_objective.visualization.plot_pareto_front(study)
fig.show()
```

Parameters

- **study** (optuna.multi_objective.study.MultiObjectiveStudy) A MultiObjectiveStudy object whose trials are plotted for their objective values.
- names (Optional[List[str]]) Objective name list used as the axis titles. If None is specified, "Objective {objective_index}" is used instead.
- include_dominated_trials (bool) A flag to include all dominated trial's objective
 values.
- axis_order (Optional [List[int]]) A list of indices indicating the axis order. If None is specified, default order is used.

Returns A plotly.graph_objs.Figure object.

Raises ValueError – If the number of objectives of study isn't 2 or 3.

Return type plotly.graph_objs._figure.Figure

Warning: Deprecated in v2.4.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

6.3.9 optuna.pruners

The *pruners* module defines a *BasePruner* class characterized by an abstract *prune()* method, which, for a given trial and its associated study, returns a boolean value representing whether the trial should be pruned. This determination is made based on stored intermediate values of the objective function, as previously reported for the trial using *optuna*. *trial.report()*. The remaining classes in this module represent child classes, inheriting from *BasePruner*, which implement different pruning strategies.

See also:

3. Efficient Optimization Algorithms tutorial explains the concept of the pruner classes and a minimal example.

See also:

User-Defined Pruner tutorial could be helpful if you want to implement your own pruner classes.

optuna.pruners.BasePruner	Base class for pruners.
optuna.pruners.MedianPruner	Pruner using the median stopping rule.
optuna.pruners.NopPruner	Pruner which never prunes trials.
optuna.pruners.PatientPruner	Pruner which wraps another pruner with tolerance.
optuna.pruners.PercentilePruner	Pruner to keep the specified percentile of the trials.
optuna.pruners.SuccessiveHalvingPruner	Pruner using Asynchronous Successive Halving Algo-
	rithm.
optuna.pruners.HyperbandPruner	Pruner using Hyperband.
optuna.pruners.ThresholdPruner	Pruner to detect outlying metrics of the trials.

optuna.pruners.BasePruner

class optuna.pruners.BasePruner

Base class for pruners.

Methods

prune(study, trial)	Judge whether the trial should be pruned based on the
	reported values.

abstract prune(study, trial)

Judge whether the trial should be pruned based on the reported values.

Note that this method is not supposed to be called by library users. Instead, <code>optuna.trial.Trial.report()</code> and <code>optuna.trial.Trial.should_prune()</code> provide user interfaces to implement pruning mechanism in an objective function.

Parameters

- **study** (optuna.study.study) Study object of the target study.
- **trial** (optuna.trial._frozen.FrozenTrial) FrozenTrial object of the target trial. Take a copy before modifying this object.

Returns A boolean value representing whether the trial should be pruned.

Return type bool

optuna.pruners.MedianPruner

Pruner using the median stopping rule.

Prune if the trial's best intermediate result is worse than median of intermediate results of previous trials at the same step.

Example

We minimize an objective function with the median stopping rule.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)
def objective(trial):
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
    clf = SGDClassifier(alpha=alpha)
    n_train_iter = 100
    for step in range(n_train_iter):
        clf.partial_fit(X_train, y_train, classes=classes)
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step)
        if trial.should_prune():
            raise optuna.TrialPruned()
    return clf.score(X_valid, y_valid)
study = optuna.create_study(
```

(continues on next page)

(continued from previous page)

```
direction="maximize",
   pruner=optuna.pruners.MedianPruner(
        n_startup_trials=5, n_warmup_steps=30, interval_steps=10
   ),
)
study.optimize(objective, n_trials=20)
```

Parameters

- n_startup_trials (int) Pruning is disabled until the given number of trials finish in the same study.
- n_warmup_steps (int) Pruning is disabled until the trial exceeds the given number of step. Note that this feature assumes that step starts at zero.
- **interval_steps** (*int*) Interval in number of steps between the pruning checks, offset by the warmup steps. If no value has been reported at the time of a pruning check, that particular check will be postponed until a value is reported.
- n_min_trials (int) Minimum number of reported trial results at a step to judge whether to prune. If the number of reported intermediate values from all trials at the current step is less than n_min_trials, the trial will not be pruned. This can be used to ensure that a minimum number of trials are run to completion without being pruned.

Return type None

Methods

prune(study, trial)	Judge whether the trial should be pruned based on the
	reported values.

prune(study, trial)

Judge whether the trial should be pruned based on the reported values.

Note that this method is not supposed to be called by library users. Instead, <code>optuna.trial.Trial.report()</code> and <code>optuna.trial.Trial.should_prune()</code> provide user interfaces to implement pruning mechanism in an objective function.

Parameters

- **study** (optuna.study.study) Study object of the target study.
- **trial** (optuna.trial._frozen.FrozenTrial) FrozenTrial object of the target trial. Take a copy before modifying this object.

Returns A boolean value representing whether the trial should be pruned.

Return type bool

optuna.pruners.NopPruner

class optuna.pruners.NopPruner

Pruner which never prunes trials.

Example

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)
def objective(trial):
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
    clf = SGDClassifier(alpha=alpha)
   n_train_iter = 100
    for step in range(n_train_iter):
        clf.partial_fit(X_train, y_train, classes=classes)
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step)
        if trial.should_prune():
            assert False, "should_prune() should always return False with this.
→pruner."
            raise optuna.TrialPruned()
    return clf.score(X_valid, y_valid)
study = optuna.create_study(direction="maximize", pruner=optuna.pruners.NopPruner())
study.optimize(objective, n_trials=20)
```

Methods

```
prune(study, trial)Judge whether the trial should be pruned based on thereported values.
```

prune(study, trial)

Judge whether the trial should be pruned based on the reported values.

Note that this method is not supposed to be called by library users. Instead, optuna.trial.Trial.report() and optuna.trial.Trial.should_prune() provide user interfaces to implement pruning

mechanism in an objective function.

Parameters

- study (optuna.study.study) Study object of the target study.
- **trial** (optuna.trial._frozen.FrozenTrial) FrozenTrial object of the target trial. Take a copy before modifying this object.

Returns A boolean value representing whether the trial should be pruned.

Return type bool

optuna.pruners.PatientPruner

class optuna.pruners.PatientPruner(wrapped_pruner, patience, min_delta=0.0)

Pruner which wraps another pruner with tolerance.

Example

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)
def objective(trial):
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
    clf = SGDClassifier(alpha=alpha)
    n_train_iter = 100
    for step in range(n_train_iter):
        clf.partial_fit(X_train, y_train, classes=classes)
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step)
        if trial.should_prune():
            raise optuna.TrialPruned()
   return clf.score(X_valid, y_valid)
study = optuna.create_study(
    direction="maximize",
   pruner=optuma.pruners.PatientPruner(optuma.pruners.MedianPruner(), patience=1),
study.optimize(objective, n_trials=20)
```

Parameters

- wrapped_pruner (Optional[optuna.pruners._base.BasePruner]) Wrapped pruner to perform pruning when PatientPruner allows a trial to be pruned. If it is None, this pruner is equivalent to early-stopping taken the intermediate values in the individual trial.
- patience (int) Pruning is disabled until the objective doesn't improve for patience consecutive steps.
- min_delta (float) Tolerance value to check whether or not the objective improves. This value should be non-negative.

Return type None

Note: Added in v2.8.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.8.0.

Methods

prune(study, trial)	Judge whether the trial should be pruned based on the
	reported values.

prune(study, trial)

Judge whether the trial should be pruned based on the reported values.

Note that this method is not supposed to be called by library users. Instead, <code>optuna.trial.Trial.report()</code> and <code>optuna.trial.Trial.should_prune()</code> provide user interfaces to implement pruning mechanism in an objective function.

Parameters

- **study** (optuna.study.study) Study object of the target study.
- **trial** (optuna.trial._frozen.FrozenTrial) FrozenTrial object of the target trial. Take a copy before modifying this object.

Returns A boolean value representing whether the trial should be pruned.

Return type bool

optuna.pruners.PercentilePruner

Pruner to keep the specified percentile of the trials.

Prune if the best intermediate value is in the bottom percentile among trials at the same step.

Example

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)
def objective(trial):
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
    clf = SGDClassifier(alpha=alpha)
    n_train_iter = 100
    for step in range(n_train_iter):
        clf.partial_fit(X_train, y_train, classes=classes)
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step)
        if trial.should_prune():
            raise optuna.TrialPruned()
    return clf.score(X_valid, y_valid)
study = optuna.create_study(
    direction="maximize",
    pruner=optuna.pruners.PercentilePruner(
        25.0, n_startup_trials=5, n_warmup_steps=30, interval_steps=10
    ),
study optimize(objective, n_trials=20)
```

Parameters

- **percentile** (*float*) Percentile which must be between 0 and 100 inclusive (e.g., When given 25.0, top of 25th percentile trials are kept).
- **n_startup_trials** (*int*) Pruning is disabled until the given number of trials finish in the same study.
- n_warmup_steps (int) Pruning is disabled until the trial exceeds the given number of step. Note that this feature assumes that step starts at zero.
- **interval_steps** (*int*) Interval in number of steps between the pruning checks, offset by the warmup steps. If no value has been reported at the time of a pruning check, that particular check will be postponed until a value is reported. Value must be at least 1.
- n_min_trials (int) Minimum number of reported trial results at a step to judge whether to prune. If the number of reported intermediate values from all trials at the current step

is less than n_min_trials, the trial will not be pruned. This can be used to ensure that a minimum number of trials are run to completion without being pruned.

Return type None

Methods

prune(study, trial)	Judge whether the trial should be pruned based on the
	reported values.

prune(study, trial)

Judge whether the trial should be pruned based on the reported values.

Note that this method is not supposed to be called by library users. Instead, <code>optuna.trial.Trial.report()</code> and <code>optuna.trial.Trial.should_prune()</code> provide user interfaces to implement pruning mechanism in an objective function.

Parameters

- **study** (optuna.study.study) Study object of the target study.
- **trial** (optuna.trial._frozen.FrozenTrial) FrozenTrial object of the target trial. Take a copy before modifying this object.

Returns A boolean value representing whether the trial should be pruned.

Return type bool

optuna.pruners.SuccessiveHalvingPruner

Pruner using Asynchronous Successive Halving Algorithm.

Successive Halving is a bandit-based algorithm to identify the best one among multiple configurations. This class implements an asynchronous version of Successive Halving. Please refer to the paper of Asynchronous Successive Halving for detailed descriptions.

Note that, this class does not take care of the parameter for the maximum resource, referred to as R in the paper. The maximum resource allocated to a trial is typically limited inside the objective function (e.g., step number in simple_pruning.py, EPOCH number in chainer_integration.py).

See also:

Please refer to report ().

Example

We minimize an objective function with SuccessiveHalvingPruner.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
```

(continues on next page)

(continued from previous page)

```
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)
def objective(trial):
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
    clf = SGDClassifier(alpha=alpha)
   n_train_iter = 100
    for step in range(n_train_iter):
        clf.partial_fit(X_train, y_train, classes=classes)
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step)
        if trial.should_prune():
            raise optuna.TrialPruned()
    return clf.score(X_valid, y_valid)
study = optuna.create_study(
    direction="maximize", pruner=optuna.pruners.SuccessiveHalvingPruner()
study.optimize(objective, n_trials=20)
```

Parameters

• min_resource (Union[str, int]) – A parameter for specifying the minimum resource allocated to a trial (in the paper this parameter is referred to as r). This parameter defaults to 'auto' where the value is determined based on a heuristic that looks at the number of required steps for the first trial to complete.

A trial is never pruned until it executes min_resource \times reduction_factor min_early_stopping_rate steps (i.e., the completion point of the first rung). When the trial completes the first rung, it will be promoted to the next rung only if the value of the trial is placed in the top $\frac{1}{\text{reduction_factor}}$ fraction of the all trials that already have reached the point (otherwise it will be pruned there). If the trial won the competition, it runs until the next completion point (i.e., min_resource \times reduction_factor $\frac{\text{min_early_stopping_rate+rung}}{\text{reduction_factor}}$ steps) and repeats the same procedure.

Note: If the step of the last intermediate value may change with each trial, please manually specify the minimum possible step to min_resource.

- **reduction_factor** (int) A parameter for specifying reduction factor of promotable trials (in the paper this parameter is referred to as η). At the completion point of each rung, about $\frac{1}{\text{reduction_factor}}$ trials will be promoted.
- min_early_stopping_rate (int) A parameter for specifying the minimum early-stopping rate (in the paper this parameter is referred to as s).

• **bootstrap_count** (*int*) – Minimum number of trials that need to complete a rung before any trial is considered for promotion into the next rung.

Return type None

Methods

<pre>prune(study, trial)</pre>	Judge whether the trial should be pruned based on the
	reported values.

prune(study, trial)

Judge whether the trial should be pruned based on the reported values.

Note that this method is not supposed to be called by library users. Instead, <code>optuna.trial.Trial.report()</code> and <code>optuna.trial.Trial.should_prune()</code> provide user interfaces to implement pruning mechanism in an objective function.

Parameters

- study (optuna.study.study) Study object of the target study.
- **trial** (optuna.trial._frozen.FrozenTrial) FrozenTrial object of the target trial. Take a copy before modifying this object.

Returns A boolean value representing whether the trial should be pruned.

Return type bool

optuna.pruners.HyperbandPruner

Pruner using Hyperband.

As SuccessiveHalving (SHA) requires the number of configurations n as its hyperparameter. For a given finite budget B, all the configurations have the resources of $\frac{B}{n}$ on average. As you can see, there will be a trade-off of B and $\frac{B}{n}$. Hyperband attacks this trade-off by trying different n values for a fixed budget.

Note:

- In the Hyperband paper, the counterpart of RandomSampler is used.
- Optuna uses TPESampler by default.
- The benchmark result shows that optuna.pruners.HyperbandPruner supports both samplers.

Note: If you use HyperbandPruner with *TPESampler*, it's recommended to consider to set larger n_trials or timeout to make full use of the characteristics of *TPESampler* because *TPESampler* uses some (by default, 10) *Trials* for its startup.

As Hyperband runs multiple *SuccessiveHalvingPruner* and collect trials based on the current *Trial*'s bracket ID, each bracket needs to observe more than 10 *Trials* for *TPESampler* to adapt its search space.

Thus, for example, if HyperbandPruner has 4 pruners in it, at least 4×10 trials are consumed for startup.

Note: Hyperband has several *SuccessiveHalvingPruner*. Each *SuccessiveHalvingPruner* is referred as "bracket" in the original paper. The number of brackets is an important factor to control the early stopping behavior of Hyperband and is automatically determined by min_resource, max_resource and reduction_factor as *The number of brackets = floor(log_{reduction_factor}(max_resource / min_resource)) + 1*. Please set reduction_factor so that the number of brackets is not too large (about 4 ~ 6 in most use cases). Please see Section 3.6 of the original paper for the detail.

See also:

Please refer to report ().

Example

We minimize an objective function with Hyperband pruning algorithm.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
classes = np.unique(y)
n_train_iter = 100
def objective(trial):
    alpha = trial.suggest_float("alpha", 0.0, 1.0)
    clf = SGDClassifier(alpha=alpha)
    for step in range(n_train_iter):
        clf.partial_fit(X_train, y_train, classes=classes)
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step)
        if trial.should_prune():
            raise optuna.TrialPruned()
    return clf.score(X_valid, y_valid)
study = optuna.create_study(
    direction="maximize",
    pruner=optuna.pruners.HyperbandPruner(
        min_resource=1, max_resource=n_train_iter, reduction_factor=3
    ),
study.optimize(objective, n_trials=20)
```

Parameters

- min_resource (int) A parameter for specifying the minimum resource allocated to a
 trial noted as r in the paper. A smaller r will give a result faster, but a larger r will
 give a better guarantee of successful judging between configurations. See the details for
 SuccessiveHalvingPruner.
- max_resource (Union[str, int]) A parameter for specifying the maximum resource allocated to a trial. R in the paper corresponds to max_resource / min_resource. This value represents and should match the maximum iteration steps (e.g., the number of epochs for neural networks). When this argument is "auto", the maximum resource is estimated according to the completed trials. The default value of this argument is "auto".

Note: With "auto", the maximum resource will be the largest step reported by *report()* in the first, or one of the first if trained in parallel, completed trial. No trials will be pruned until the maximum resource is determined.

Note: If the step of the last intermediate value may change with each trial, please manually specify the maximum possible step to max_resource.

- **reduction_factor** (int) A parameter for specifying reduction factor of promotable trials noted as η in the paper. See the details for *SuccessiveHalvingPruner*.
- **bootstrap_count** (*int*) Parameter specifying the number of trials required in a rung before any trial can be promoted. Incompatible with max_resouce is "auto". See the details for *SuccessiveHalvingPruner*.

Return type None

Methods

<pre>prune(study, trial)</pre>	Judge whether the trial should be pruned based on the
	reported values.

prune(study, trial)

Judge whether the trial should be pruned based on the reported values.

Note that this method is not supposed to be called by library users. Instead, <code>optuna.trial.Trial.report()</code> and <code>optuna.trial.Trial.should_prune()</code> provide user interfaces to implement pruning mechanism in an objective function.

Parameters

- **study** (optuna.study.study) Study object of the target study.
- **trial** (optuna.trial._frozen.FrozenTrial) FrozenTrial object of the target trial. Take a copy before modifying this object.

Returns A boolean value representing whether the trial should be pruned.

Return type bool

optuna.pruners.ThresholdPruner

class optuna.pruners.**ThresholdPruner**(*lower=None*, *upper=None*, *n_warmup_steps=0*, *interval_steps=1*)

Pruner to detect outlying metrics of the trials.

Prune if a metric exceeds upper threshold, falls behind lower threshold or reaches nan.

Example

```
from optuna import create_study
from optuna.pruners import ThresholdPruner
from optuna import TrialPruned
def objective_for_upper(trial):
    for step, y in enumerate(ys_for_upper):
        trial.report(y, step)
        if trial.should_prune():
            raise TrialPruned()
    return ys_for_upper[-1]
def objective_for_lower(trial):
    for step, y in enumerate(ys_for_lower):
        trial.report(y, step)
        if trial.should_prune():
            raise TrialPruned()
    return ys_for_lower[-1]
ys_for_upper = [0.0, 0.1, 0.2, 0.5, 1.2]
ys_for_lower = [100.0, 90.0, 0.1, 0.0, -1]
study = create_study(pruner=ThresholdPruner(upper=1.0))
study.optimize(objective_for_upper, n_trials=10)
study = create_study(pruner=ThresholdPruner(lower=0.0))
study optimize(objective_for_lower, n_trials=10)
```

Parameters

- **lower** (*Optional[float]*) A minimum value which determines whether pruner prunes or not. If an intermediate value is smaller than lower, it prunes.
- **upper** (Optional[float]) A maximum value which determines whether pruner prunes or not. If an intermediate value is larger than upper, it prunes.
- n_warmup_steps (int) Pruning is disabled if the step is less than the given number of warmup steps.
- **interval_steps** (*int*) Interval in number of steps between the pruning checks, offset by the warmup steps. If no value has been reported at the time of a pruning check, that particular check will be postponed until a value is reported. Value must be at least 1.

Return type None

Methods

prune(study, trial)	Judge whether the trial should be pruned based on the
	reported values.

prune(study, trial)

Judge whether the trial should be pruned based on the reported values.

Note that this method is not supposed to be called by library users. Instead, <code>optuna.trial.Trial.report()</code> and <code>optuna.trial.Trial.should_prune()</code> provide user interfaces to implement pruning mechanism in an objective function.

Parameters

- **study** (optuna.study.study) Study object of the target study.
- **trial** (optuna.trial._frozen.FrozenTrial) FrozenTrial object of the target trial. Take a copy before modifying this object.

Returns A boolean value representing whether the trial should be pruned.

Return type bool

6.3.10 optuna.samplers

The *samplers* module defines a base class for parameter sampling as described extensively in *BaseSampler*. The remaining classes in this module represent child classes, deriving from *BaseSampler*, which implement different sampling strategies.

See also:

3. Efficient Optimization Algorithms tutorial explains the overview of the sampler classes.

See also:

User-Defined Sampler tutorial could be helpful if you want to implement your own sampler classes.

optuna.samplers.BaseSampler	Base class for samplers.
optuna.samplers.GridSampler	Sampler using grid search.
optuna.samplers.RandomSampler	Sampler using random sampling.
optuna.samplers.TPESampler	Sampler using TPE (Tree-structured Parzen Estimator)
	algorithm.
optuna.samplers.CmaEsSampler	A sampler using cmaes as the backend.
optuna.samplers.PartialFixedSampler	Sampler with partially fixed parameters.
optuna.samplers.NSGAIISampler	Multi-objective sampler using the NSGA-II algorithm.
optuna.samplers.MOTPESampler	Multi-objective sampler using the MOTPE algorithm.
optuna.samplers.QMCSampler	A Quasi Monte Carlo Sampler that generates low-
	discrepancy sequences.
optuna.samplers.IntersectionSearchSpace	A class to calculate the intersection search space of a
	Study.
optuna.samplers.intersection_search_space	Return the intersection search space of the <i>Study</i> .

optuna.samplers.BaseSampler

class optuna.samplers.BaseSampler

Base class for samplers.


Optuna combines two types of sampling strategies, which are called *relative sampling* and *independent sampling*.

The relative sampling determines values of multiple parameters simultaneously so that sampling algorithms can use relationship between parameters (e.g., correlation). Target parameters of the relative sampling are described in a relative search space, which is determined by <code>infer_relative_search_space()</code>.

The independent sampling determines a value of a single parameter without considering any relationship between parameters. Target parameters of the independent sampling are the parameters not described in the relative search space.

More specifically, parameters are sampled by the following procedure. At the beginning of a trial, <code>infer_relative_search_space()</code> is called to determine the relative search space for the trial. Then, <code>sample_relative()</code> is invoked to sample parameters from the relative search space. During the execution of the objective function, <code>sample_independent()</code> is used to sample parameters that don't belong to the relative search space.

The following figure depicts the lifetime of a trial and how the above three methods are called in the trial.



Methods

after_trial(study, trial, state, values)	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **state** (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional [Sequence [float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

abstract infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before $sample_relative()$ method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using $sample_independent()$ method.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

abstract sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- param_name (str) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

abstract sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.samplers.GridSampler

```
class optuna.samplers.GridSampler(search_space)
```

Sampler using grid search.

With *GridSampler*, the trials suggest all combinations of parameters in the given search space during the study.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_int("y", -100, 100)
    return x**2 + y**2

search_space = {"x": [-50, 0, 50], "y": [-99, 0, 99]}
study = optuna.create_study(sampler=optuna.samplers.GridSampler(search_space))
study.optimize(objective)
```

Note: *GridSampler* automatically stops the optimization if all combinations in the passed search_space have already been evaluated, internally invoking the *stop()* method.

Note: *GridSampler* does not take care of a parameter's quantization specified by discrete suggest methods but just samples one of values specified in the search space. E.g., in the following code snippet, either of -0.5 or 0.5 is sampled as x instead of an integer point.

```
def objective(trial):
    # The following suggest method specifies integer points between -5 and 5.
    x = trial.suggest_float("x", -5, 5, step=1)
    return x**2

# Non-int points are specified in the grid.
search_space = {"x": [-0.5, 0.5]}
study = optuna.create_study(sampler=optuna.samplers.GridSampler(search_space))
study.optimize(objective, n_trials=2)
```

Note: A parameter configuration in the grid is not considered finished until its trial is finished. Therefore, during distributed optimization where trials run concurrently, different workers will occasionally suggest the

same parameter configuration. The total number of actual trials may therefore exceed the size of the grid.

Note: The grid is randomly shuffled and the order in which parameter configurations are suggested may vary. This is to reduce duplicate suggestions during distributed optimization.

Note: All parameters must be specified when using *GridSampler* with *enqueue_trial()*.

Parameters search_space (Mapping[str, Sequence[Union[None, bool, int, float, str]]]) - A dictionary whose key and value are a parameter name and the corresponding candidates of values, respectively.

Return type None

Methods

<pre>after_trial(study, trial, state, values)</pre>	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- state (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional[Sequence[float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to *intersection_search_space()* as an implementation of *infer_relative_search_space()*.

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- param_name (str) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.samplers.RandomSampler

```
class optuna.samplers.RandomSampler(seed=None)
```

Sampler using random sampling.

This sampler is based on *independent sampling*. See also *BaseSampler* for more details of 'independent sampling'.

Example

```
import optuna
from optuna.samplers import RandomSampler

def objective(trial):
    x = trial.suggest_float("x", -5, 5)
    return x**2

study = optuna.create_study(sampler=RandomSampler())
study.optimize(objective, n_trials=10)
```

Parameters seed (Optional[int]) – Seed for random number generator.

Return type None

Methods

<pre>after_trial(study, trial, state, values)</pre>	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
sample_relative(study, trial, search_space)	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **state** (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional [Sequence [float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before $sample_relative()$ method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using $sample_independent()$ method.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- param_name (str) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

```
Return type Dict[str, Any]
```

optuna.samplers.TPESampler

Sampler using TPE (Tree-structured Parzen Estimator) algorithm.

This sampler is based on *independent sampling*. See also *BaseSampler* for more details of 'independent sampling'.

On each trial, for each parameter, TPE fits one Gaussian Mixture Model (GMM) 1(x) to the set of parameter values associated with the best objective values, and another GMM g(x) to the remaining parameter values. It chooses the parameter value x that maximizes the ratio 1(x)/g(x).

For further information about TPE algorithm, please refer to the following papers:

- Algorithms for Hyper-Parameter Optimization
- Making a Science of Model Search: Hyperparameter Optimization in Hundreds of Dimensions for Vision Architectures
- · Multiobjective tree-structured parzen estimator for computationally expensive optimization problems

Example

```
import optuna
from optuna.samplers import TPESampler

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return x**2

study = optuna.create_study(sampler=TPESampler())
study.optimize(objective, n_trials=10)
```

Parameters

- **consider_prior** (*bool*) Enhance the stability of Parzen estimator by imposing a Gaussian prior when True. The prior is only effective if the sampling distribution is either *FloatDistribution*, or *IntDistribution*.
- **prior_weight** (*float*) The weight of the prior. This argument is used in *FloatDistribution*, *IntDistribution*, and *CategoricalDistribution*.
- **consider_magic_clip** (*bool*) Enable a heuristic to limit the smallest variances of Gaussians used in the Parzen estimator.
- **consider_endpoints** (*bool*) Take endpoints of domains into account when calculating variances of Gaussians in Parzen estimator. See the original paper for details on the heuristics to calculate the variances.

- **n_startup_trials** (*int*) The random sampling is used instead of the TPE algorithm until the given number of trials finish in the same study.
- n_ei_candidates (int) Number of candidate samples used to calculate the expected improvement.
- gamma (Callable[[int], int]) A function that takes the number of finished trials and returns the number of trials to form a density function for samples with low grains. See the original paper for more details.
- weights (Callable[[int], numpy.ndarray]) A function that takes the number of finished trials and returns a weight for them. See Making a Science of Model Search: Hyperparameter Optimization in Hundreds of Dimensions for Vision Architectures for more details.

Note: In the multi-objective case, this argument is only used to compute the weights of bad trials, i.e., trials to construct g(x) in the paper). The weights of good trials, i.e., trials to construct l(x), are computed by a rule based on the hypervolume contribution proposed in the paper of MOTPE.

- **seed** (Optional[int]) Seed for random number generator.
- **multivariate** (*boo1*) If this is True, the multivariate TPE is used when suggesting parameters. The multivariate TPE is reported to outperform the independent TPE. See BOHB: Robust and Efficient Hyperparameter Optimization at Scale for more details.

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

• group (bool) – If this and multivariate are True, the multivariate TPE with the group decomposed search space is used when suggesting parameters. The sampling algorithm decomposes the search space based on past trials and samples from the joint distribution in each decomposed subspace. The decomposed subspaces are a partition of the whole search space. Each subspace is a maximal subset of the whole search space, which satisfies the following: for a trial in completed trials, the intersection of the subspace and the search space of the trial becomes subspace itself or an empty set. Sampling from the joint distribution on the subspace is realized by multivariate TPE.

Note: Added in v2.8.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.8.0.

Example:

```
import optuna

def objective(trial):
    x = trial.suggest_categorical("x", ["A", "B"])
    if x == "A":
        return trial.suggest_float("y", -10, 10)
    else:
        return trial.suggest_int("z", -10, 10)
```

(continues on next page)

(continued from previous page)

```
sampler = optuna.samplers.TPESampler(multivariate=True, group=True)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)
```

- warn_independent_sampling (bool) If this is True and multivariate=True, a warning message is emitted when the value of a parameter is sampled by using an independent sampler. If multivariate=False, this flag has no effect.
- **constant_liar** (*bool*) If True, penalize running trials to avoid suggesting parameter configurations nearby.

Note: Abnormally terminated trials often leave behind a record with a state of *RUNNING* in the storage. Such "zombie" trial parameters will be avoided by the constant liar algorithm during subsequent sampling. When using an *RDBStorage*, it is possible to enable the heartbeat_interval to change the records for abnormally terminated trials to *FAIL*.

Note: It is recommended to set this value to True during distributed optimization to avoid having multiple workers evaluating similar parameter configurations. In particular, if each objective function evaluation is costly and the durations of the running states are significant, and/or the number of workers is high.

Note: Added in v2.8.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.8.0.

Raises ValueError – If multivariate is False and group is True.

Return type None

Methods

after_trial(study, trial, state, values)	Trial post-processing.
hyperopt_parameters()	Return the the default parameters of hyperopt
	(v0.1.2).
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- state (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional[Sequence[float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

static hyperopt_parameters()

Return the default parameters of hyperopt (v0.1.2).

TPESampler can be instantiated with the parameters returned by this method.

Example

Create a *TPESampler* instance with the default parameters of hyperopt.

```
import optuna
from optuna.samplers import TPESampler

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return x**2

sampler = TPESampler(**TPESampler.hyperopt_parameters())
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)
```

Returns A dictionary containing the default parameters of hyperopt.

```
Return type Dict[str, Any]
```

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- param_name (str) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

• study (optuna.study.study) - Target study object.

- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

```
Return type Dict[str, Any]
```

optuna.samplers.CmaEsSampler

```
class optuna.samplers.CmaEsSampler(x0=None, sigma0=None, n_startup_trials=1, independent_sampler=None, warn_independent_sampling=True, seed=None, *, consider_pruned_trials=False, restart_strategy=None, inc_popsize=2, use_separable_cma=False, source_trials=None)
```

A sampler using cmaes as the backend.

Example

Optimize a simple quadratic function by using CmaEsSampler.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -1, 1)
    y = trial.suggest_int("y", -1, 1)
    return x**2 + y

sampler = optuna.samplers.CmaEsSampler()
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=20)
```

Please note that this sampler does not support CategoricalDistribution. However, FloatDistribution with step, (suggest_float()) and IntDistribution (suggest_int()) are supported.

If your search space contains categorical parameters, I recommend you to use *TPESampler* instead. Furthermore, there is room for performance improvements in parallel optimization settings. This sampler cannot use some trials for updating the parameters of multivariate normal distribution.

For further information about CMA-ES algorithm, please refer to the following papers:

- N. Hansen, The CMA Evolution Strategy: A Tutorial. arXiv:1604.00772, 2016.
- A. Auger and N. Hansen. A restart CMA evolution strategy with increasing population size. In Proceedings of the IEEE Congress on Evolutionary Computation (CEC 2005), pages 1769–1776. IEEE Press, 2005.
- Raymond Ros, Nikolaus Hansen. A Simple Modification in CMA-ES Achieving Linear Time and Space Complexity. 10th International Conference on Parallel Problem Solving From Nature, Sep 2008, Dortmund, Germany. inria-00287367.
- Masahiro Nomura, Shuhei Watanabe, Youhei Akimoto, Yoshihiko Ozaki, Masaki Onishi. Warm Starting CMA-ES for Hyperparameter Optimization, AAAI. 2021.

See also:

You can also use optuma.integration.PyCmaSampler which is a sampler using cma library as the backend.

Parameters

- **x0** (Optional [Dict[str, Any]]) A dictionary of an initial parameter values for CMA-ES. By default, the mean of low and high for each distribution is used. Note that **x0** is sampled uniformly within the search space domain for each restart if you specify restart_strategy argument.
- **sigma0** (Optional [float]) Initial standard deviation of CMA-ES. By default, sigma0 is set to min_range / 6, where min_range denotes the minimum range of the distributions in the search space.
- **seed** (Optional[int]) A random seed for CMA-ES.
- n_startup_trials (int) The independent sampling is used instead of the CMA-ES algorithm until the given number of trials finish in the same study.
- independent_sampler (Optional[optuna.samplers._base.BaseSampler]) A BaseSampler instance that is used for independent sampling. The parameters not contained in the relative search space are sampled by this sampler. The search space for CmaEsSampler is determined by intersection_search_space().

If None is specified, RandomSampler is used as the default.

See also:

optuna.samplers module provides built-in independent samplers such as RandomSampler and TPESampler.

• warn_independent_sampling (bool) – If this is True, a warning message is emitted when the value of a parameter is sampled by using an independent sampler.

Note that the parameters of the first trial in a study are always sampled via an independent sampler, so no warning messages are emitted in this case.

• **restart_strategy** (Optional[str]) — Strategy for restarting CMA-ES optimization when converges to a local minimum. If given None, CMA-ES will not restart (default). If given 'ipop', CMA-ES will restart with increasing population size. Please see also inc_popsize parameter.

Note: Added in v2.1.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.1.0.

- **inc_popsize** (*int*) Multiplier for increasing population size before each restart. This argument will be used when setting restart_strategy = 'ipop'.
- **consider_pruned_trials** (*bool*) If this is True, the PRUNED trials are considered for sampling.

Note: Added in v2.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.0.0.

Note: It is suggested to set this flag False when the *MedianPruner* is used. On the other hand, it is suggested to set this flag True when the *HyperbandPruner* is used. Please see

the benchmark result for the details.

• use_separable_cma (bool) – If this is True, the covariance matrix is constrained to be diagonal. Due to reduce the model complexity, the learning rate for the covariance matrix is increased. Consequently, this algorithm outperforms CMA-ES on separable functions.

Note: Added in v2.6.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.6.0.

• source_trials (Optional[List[optuna.trial._frozen.FrozenTrial]]) - This option is for Warm Starting CMA-ES, a method to transfer prior knowledge on similar HPO tasks through the initialization of CMA-ES. This method estimates a promising distribution from source_trials and generates the parameter of multivariate gaussian distribution. Please note that it is prohibited to use x0, sigma0, or use_separable_cma argument together.

Note: Added in v2.6.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.6.0.

Raises ValueError - If restart_strategy is not 'ipop' or None.

Return type None

Methods

after_trial(study, trial, state, values)	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
sample_relative(study, trial, search_space)	Sample parameters in a given search space.

after_trial(*study*, *trial*, *state*, *values*)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- state (optuna.trial._state.TrialState) Resulting trial state.

• values (Optional[Sequence[float]]) – Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the Study instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

```
sample_relative(study, trial, search_space)
```

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.samplers.PartialFixedSampler

class optuna.samplers.PartialFixedSampler(fixed_params, base_sampler)

Sampler with partially fixed parameters.

New in version 2.4.0.

Example

After several steps of optimization, you can fix the value of y and re-optimize it.

(continues on next page)

(continued from previous page)

```
study.sampler = partial_sampler
study.optimize(objective, n_trials=10)
```

Parameters

- **fixed_params** (*Dict[str, Any]*) A dictionary of parameters to be fixed.
- base_sampler (optuna.samplers._base.BaseSampler) A sampler which samples unfixed parameters.

Return type None

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Methods

after_trial(study, trial, state, values)	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **state** (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional[Sequence[float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to intersection_search_space() as an implementation of infer_relative_search_space().

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

```
sample_relative(study, trial, search_space)
```

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.samplers.NSGAllSampler

Multi-objective sampler using the NSGA-II algorithm.

NSGA-II stands for "Nondominated Sorting Genetic Algorithm II", which is a well known, fast and elitist multi-objective genetic algorithm.

For further information about NSGA-II, please refer to the following paper:

• A fast and elitist multiobjective genetic algorithm: NSGA-II

Parameters

- **population_size** (*int*) Number of individuals (trials) in a generation.
- mutation_prob (Optional[float]) Probability of mutating each parameter when creating a new individual. If None is specified, the value 1.0 / len(parent_trial. params) is used where parent_trial is the parent trial of the target individual.
- **crossover** (Optional[optuna.samplers.nsgaii._crossovers._base. BaseCrossover]) Crossover to be applied when creating child individuals. The available crossovers are listed here: https://optuna.readthedocs.io/en/stable/reference/samplers/nsgaii.html.

UniformCrossover is always applied to parameters sampled from *CategoricalDistribution*, and by default for parameters sampled from other distributions unless this argument is specified.

For more information on each of the crossover method, please refer to specific crossover documentation.

- crossover_prob (float) Probability that a crossover (parameters swapping between parents) will occur when creating a new individual.
- **swapping_prob** (*float*) Probability of swapping each parameter of the parents during crossover.
- **seed** (Optional[int]) Seed for random number generator.
- constraints_func (Optional[Callable[[optuna.trial._frozen. FrozenTrial], Sequence[float]]]) An optional function that computes the objective constraints. It must take a FrozenTrial and return the constraints. The return value must be a sequence of float s. A value strictly larger than 0 means that a constraints is violated. A value equal to or smaller than 0 is considered feasible. If constraints_func returns more than one value for a trial, that trial is considered feasible if and only if all values are equal to 0 or smaller.

The constraints_func will be evaluated after each successful trial. The function won't be called when trials fail or they are pruned, but this behavior is subject to change in the future releases.

The constraints are handled by the constrained domination. A trial x is said to constrained-dominate a trial y, if any of the following conditions is true:

- 1. Trial x is feasible and trial y is not.
- 2. Trial x and y are both infeasible, but trial x has a smaller overall violation.
- 3. Trial x and y are feasible and trial x dominates trial y.

Note: Added in v2.5.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.5.0.

Raises ValueError – If crossover is not instance of *BaseCrossover*. Or, if population_size <= n_parents. The *n_parents* is determined by each crossover. For *UNDXCrossover* and *SPXCrossover*, n_parents=3, and for the other algorithms, n_parents=2.

Return type None

Methods

after_trial(study, trial, state, values)	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- state (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional[Sequence[float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to *intersection_search_space()* as an implementation of *infer_relative_search_space()*.

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by <code>sample_relative()</code> method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- param_name (str) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type *Any*

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type Dict[str, Any]

optuna.samplers.MOTPESampler

Multi-objective sampler using the MOTPE algorithm.

This sampler is a multiobjective version of TPESampler.

For further information about MOTPE algorithm, please refer to the following paper:

• Multiobjective tree-structured parzen estimator for computationally expensive optimization problems

Parameters

- **consider_prior** (*bool*) Enhance the stability of Parzen estimator by imposing a Gaussian prior when True. The prior is only effective if the sampling distribution is either *FloatDistribution*, or *IntDistribution*.
- prior_weight (float) The weight of the prior. This argument is used in FloatDistribution, IntDistribution, and CategoricalDistribution.
- **consider_magic_clip** (*bool*) Enable a heuristic to limit the smallest variances of Gaussians used in the Parzen estimator.
- **consider_endpoints** (*bool*) Take endpoints of domains into account when calculating variances of Gaussians in Parzen estimator. See the original paper for details on the heuristics to calculate the variances.
- n_startup_trials (int) The random sampling is used instead of the MOTPE algorithm until the given number of trials finish in the same study. 11 * number of variables 1 is recommended in the original paper.
- **n_ehvi_candidates** (*int*) Number of candidate samples used to calculate the expected hypervolume improvement.
- gamma (Callable[[int], int]) A function that takes the number of finished trials and returns the number of trials to form a density function for samples with low grains. See the original paper for more details.
- weights_above (Callable[[int], numpy.ndarray]) A function that takes the number of finished trials and returns a weight for them. As default, weights are automatically calculated by the MOTPE's default strategy.
- **seed** (Optional[int]) Seed for random number generator.

Return type None

Note: Initialization with Latin hypercube sampling may improve optimization performance. However, the current implementation only supports initialization with random sampling.

Example

```
import optuna
seed = 128
num_variables = 2
n_startup_trials = 11 * num_variables - 1

def objective(trial):
    x = []
    for i in range(1, num_variables + 1):
        x.append(trial.suggest_float(f"x{i}", 0.0, 2.0 * i))
    return x

sampler = optuna.samplers.MOTPESampler(
    n_startup_trials=n_startup_trials, n_ehvi_candidates=24, seed=seed
)
```

(continues on next page)

(continued from previous page)

```
study = optuna.create_study(directions=["minimize"] * num_variables,

sampler=sampler)

study.optimize(objective, n_trials=n_startup_trials + 10)
```

Warning: Deprecated in v2.9.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v4.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v2.9.0.

Methods

Trial post-processing.
Return the the default parameters of hyperopt
(v0.1.2).
Infer the search space that will be used by relative
sampling in the target trial.
Reseed sampler's random number generator.
Sample a parameter for a given distribution.
Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- $\bullet \ \ \textbf{state} \ (\texttt{optuna.trial}._\texttt{state}. \texttt{TrialState}) Resulting \ trial \ state.$
- values (Optional[Sequence[float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

static hyperopt_parameters()

Return the the default parameters of hyperopt (v0.1.2).

TPESampler can be instantiated with the parameters returned by this method.

Example

Create a *TPESampler* instance with the default parameters of hyperopt.

```
import optuna
from optuna.samplers import TPESampler

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return x**2

sampler = TPESampler(**TPESampler.hyperopt_parameters())
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)
```

Returns A dictionary containing the default parameters of hyperopt.

Return type *Dict*[str, *Any*]

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before $sample_relative()$ method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using $sample_independent()$ method.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

```
Please refer to intersection_search_space() as an implementation of infer_relative_search_space().
```

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

```
sample_independent(study, trial, param name, param distribution)
```

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by $sample_relative()$ method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type *Dict*[str, *Any*]

optuna.samplers.QMCSampler

A Quasi Monte Carlo Sampler that generates low-discrepancy sequences.

Quasi Monte Carlo (QMC) sequences are designed to have lower discrepancies than standard random sequences. They are known to perform better than the standard randam sequences in hyperparameter optimization.

For further information about the use of QMC sequences for hyperparameter optimization, please refer to the following paper:

• Bergstra, James, and Yoshua Bengio. Random search for hyper-parameter optimization. Journal of machine learning research 13.2, 2012.

We use the QMC implementations in Scipy. For the details of the QMC algorithm, see the Scipy API references on scipy.stats.qmc.

Note: The search space of the sampler is determined by either previous trials in the study or the first trial that this sampler samples.

If there are previous trials in the study, QMCSamper infers its search space using the trial which was created first in the study.

Otherwise (if the study has no previous trials), *QMCSampler* samples the first trial using its *independent_sampler* and then infers the search space in the second trial.

As mentioned above, the search space of the QMCSampler is determined by the first trial of the study. Once the search space is determined, it cannot be changed afterwards.

Parameters

• qmc_type (str) – The type of QMC sequence to be sampled. This must be one of "halton" and "sobol". Default is "sobol".

Note: Sobol' sequence is designed to have low-discrepancy property when the number of samples is $n=2^m$ for each positive integer m. When it is possible to pre-specify the number of trials suggested by QMCSampler, it is recommended that the number of trials should be set as power of two.

- **scramble** (*bool*) If this option is True, scrambling (randomization) is applied to the QMC sequences.
- **seed** (*Optional[int]*) A seed for *QMCSampler*. This argument is used only when *scramble* is True. If this is None, the seed is initialized randomly. Default is None.

Note: When using multiple *QMCSampler*'s in parallel and/or distributed optimization, all the samplers must share the same seed when the *scrambling* is enabled. Otherwise, the low-discrepancy property of the samples will be degraded.

• **independent_sampler** (Optional[optuna.samplers._base.BaseSampler]) — A BaseSampler instance that is used for independent sampling. The first trial of the study and the parameters not contained in the relative search space are sampled by this sampler.

If None is specified, RandomSampler is used as the default.

See also:

samplers module provides built-in independent samplers such as RandomSampler and TPESampler.

• warn_independent_sampling (bool) – If this is True, a warning message is emitted when the value of a parameter is sampled by using an independent sampler.

Note that the parameters of the first trial in a study are sampled via an independent sampler in most cases, so no warning messages are emitted in such cases.

• warn_asyncronous_seeding (bool) – If this is True, a warning message is emitted when the scrambling (randomization) is applied to the QMC sequence and the random seed of the sampler is not set manually.

Note: When using parallel and/or distributed optimization without manually setting the seed, the seed is set randomly for each instances of *QMCSampler* for different workers, which ends up asyncronous seeding for multiple samplers used in the optimization.

See also:

See parameter seed in QMCSampler.

Raises ValueError – If qmc_type is not one of 'halton' and 'sobol'.

Return type None

Example

Optimize a simple quadratic function by using QMCSampler.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -1, 1)
    y = trial.suggest_int("y", -1, 1)
    return x**2 + y

sampler = optuna.samplers.QMCSampler()
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=8)
```

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Methods

after_trial(study, trial, state, values)	Trial post-processing.
<pre>infer_relative_search_space(study, trial)</pre>	Infer the search space that will be used by relative
	sampling in the target trial.
reseed_rng()	Reseed sampler's random number generator.
<pre>sample_independent(study, trial, param_name,</pre>	Sample a parameter for a given distribution.
)	
<pre>sample_relative(study, trial, search_space)</pre>	Sample parameters in a given search space.

after_trial(study, trial, state, values)

Trial post-processing.

This method is called after the objective function returns and right before the trials is finished and its state is stored.

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- state (optuna.trial._state.TrialState) Resulting trial state.
- values (Optional[Sequence[float]]) Resulting trial values. Guaranteed to not be None if trial succeeded.

Return type None

infer_relative_search_space(study, trial)

Infer the search space that will be used by relative sampling in the target trial.

This method is called right before <code>sample_relative()</code> method, and the search space returned by this method is passed to it. The parameters not contained in the search space will be sampled by using <code>sample_independent()</code> method.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

See also:

Please refer to *intersection_search_space()* as an implementation of *infer_relative_search_space()*.

reseed_rng()

Reseed sampler's random number generator.

This method is called by the *Study* instance if trials are executed in parallel with the option n_jobs>1. In that case, the sampler instance will be replicated including the state of the random number generator, and they may suggest the same values. To prevent this issue, this method assigns a different seed to each random number generator.

Return type None

sample_independent(study, trial, param_name, param_distribution)

Sample a parameter for a given distribution.

This method is called only for the parameters not contained in the search space returned by <code>sample_relative()</code> method. This method is suitable for sampling algorithms that do not use relationship between parameters such as random sampling and TPE.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- **study** (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **param_name** (*str*) Name of the sampled parameter.
- param_distribution (optuna.distributions.BaseDistribution) Distribution object that specifies a prior and/or scale of the sampling algorithm.

Returns A parameter value.

Return type Any

sample_relative(study, trial, search_space)

Sample parameters in a given search space.

This method is called once at the beginning of each trial, i.e., right before the evaluation of the objective function. This method is suitable for sampling algorithms that use relationship between parameters such as Gaussian Process and CMA-ES.

Note: The failed trials are ignored by any build-in samplers when they sample new parameters. Thus, failed trials are regarded as deleted in the samplers' perspective.

Parameters

- study (optuna.study.study) Target study object.
- **trial** (optuna.trial._frozen.FrozenTrial) Target trial object. Take a copy before modifying this object.
- **search_space** (Dict[str, optuna.distributions.BaseDistribution]) The search space returned by infer_relative_search_space().

Returns A dictionary containing the parameter names and the values.

Return type Dict[str, Any]

optuna.samplers.IntersectionSearchSpace

class optuna.samplers.IntersectionSearchSpace(include_pruned=False)

A class to calculate the intersection search space of a *Study*.

Intersection search space contains the intersection of parameter distributions that have been suggested in the completed trials of the study so far. If there are multiple parameters that have the same name but different distributions, neither is included in the resulting search space (i.e., the parameters with dynamic value ranges are excluded).

Note that an instance of this class is supposed to be used for only one study. If different studies are passed to *calculate()*, a ValueError is raised.

Parameters include_pruned (bool) – Whether pruned trials should be included in the search space.

Return type None

Methods

calculate(study[, ordered_dict])

Returns the intersection search space of the *Study*.

calculate(study, ordered dict=False)

Returns the intersection search space of the Study.

Parameters

- **study** (optuna.study.study) A study with completed trials.
- **ordered_dict** (*bool*) A boolean flag determining the return type. If False, the returned object will be a dict. If True, the returned object will be an collections. OrderedDict sorted by keys, i.e. parameter names.

Returns A dictionary containing the parameter names and parameter's distributions.

Raises ValueError – If different studies are passed into this method.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

optuna.samplers.intersection_search_space

optuna.samplers.intersection_search_space(study, ordered_dict=False, include_pruned=False)

Return the intersection search space of the Study.

Intersection search space contains the intersection of parameter distributions that have been suggested in the completed trials of the study so far. If there are multiple parameters that have the same name but different distributions, neither is included in the resulting search space (i.e., the parameters with dynamic value ranges are excluded).

Note: *IntersectionSearchSpace* provides the same functionality with a much faster way. Please consider using it if you want to reduce execution time as much as possible.

Parameters

- **study** (optuna.study.study) A study with completed trials.
- **ordered_dict** (*bool*) A boolean flag determining the return type. If False, the returned object will be a dict. If True, the returned object will be an collections.OrderedDict sorted by keys, i.e. parameter names.
- include_pruned (boo1) Whether pruned trials should be included in the search space.

Returns A dictionary containing the parameter names and parameter's distributions.

Return type *Dict*[str, optuna.distributions.BaseDistribution]

optuna.samplers.nsgaii

The nsgaii module defines crossover operations used by NSGAIISampler.

optuna.samplers.nsgaii.BaseCrossover	Base class for crossovers.
optuna.samplers.nsgaii.UniformCrossover	An Uniform Crossover operation used by
	NSGAIISampler.
optuna.samplers.nsgaii.BLXAlphaCrossover	A Blend Crossover operation used by NSGAIISampler.
optuna.samplers.nsgaii.SPXCrossover	A Simplex Crossover operation used by
	NSGAIISampler.
optuna.samplers.nsgaii.SBXCrossover	A Simulated Binary Crossover operation used by
	NSGAIISampler.
optuna.samplers.nsgaii.VSBXCrossover	A modified Simulated Binary Crossover operation used
	by NSGAIISampler.
optuna.samplers.nsgaii.UNDXCrossover	An Unimodal Normal Distribution Crossover used by
	NSGAIISampler.

optuna.samplers.nsgaii.BaseCrossover

class optuna.samplers.nsgaii.BaseCrossover

Base class for crossovers.

A crossover operation is used by NSGAIISampler to create new parameter combination from parameters of n parent individuals.

Note: Concrete implementations of this class are expected to only accept parameters from numerical distributions. At the moment, only crossover operation for categorical parameters (uniform crossover) is built-in into *NSGAIISampler*.

Methods

crossover(parents_params, rng, study,)	Perform crossover of selected parent individuals.

Attributes

n_parents	Number of parent individuals required to perform
	crossover.

abstract crossover(parents_params, rng, study, search_space_bounds)

Perform crossover of selected parent individuals.

This method is called in sample_relative().

Parameters

• parents_params (numpy.ndarray) — A numpy.ndarray with dimensions num_parents x num_parameters. Represents a parameter space for each parent individual. This space is continuous for numerical parameters.

- rng (numpy.random.mtrand.RandomState) An instance of numpy.random. RandomState.
- **study** (optuna.study.study) Target study object.
- search_space_bounds (numpy.ndarray) A numpy.ndarray with dimensions len_search_space x 2 representing numerical distribution bounds constructed from transformed search space.

Returns A 1-dimensional numpy.ndarray containing new parameter combination.

Return type numpy.ndarray

abstract property n_parents: int

Number of parent individuals required to perform crossover.

optuna.samplers.nsgaii.UniformCrossover

class optuna.samplers.nsgaii.UniformCrossover(swapping_prob=0.5)

An Uniform Crossover operation used by NSGAIISampler.

Select each parameter with equal probability from the two parent individuals. For further information about uniform crossover, please refer to the following paper:

• Gilbert Syswerda. 1989. Uniform Crossover in Genetic Algorithms. In Proceedings of the 3rd International Conference on Genetic Algorithms. Morgan Kaufmann Publishers Inc., San Francisco, CA, USA, 2-9.

Parameters swapping_prob (float) – Probability of swapping each parameter of the parents during crossover.

Return type None

Methods

crossover(parents_params, rng, study, ...)

Perform crossover of selected parent individuals.

Attributes

n_parents

crossover(parents_params, rng, study, search_space_bounds)

Perform crossover of selected parent individuals.

This method is called in sample_relative().

Parameters

- parents_params (numpy.ndarray) A numpy.ndarray with dimensions num_parents x num_parameters. Represents a parameter space for each parent individual. This space is continuous for numerical parameters.
- rng (numpy.random.mtrand.RandomState) An instance of numpy.random. RandomState.

- **study** (optuna.study.study) Target study object.
- search_space_bounds (numpy.ndarray) A numpy.ndarray with dimensions len_search_space x 2 representing numerical distribution bounds constructed from transformed search space.

Returns A 1-dimensional numpy.ndarray containing new parameter combination.

Return type numpy.ndarray

optuna.samplers.nsgaii.BLXAlphaCrossover

class optuna.samplers.nsgaii.BLXAlphaCrossover(alpha=0.5)

A Blend Crossover operation used by NSGAIISampler.

Uniformly samples child individuals from the hyper-rectangles created by the two parent individuals. For further information about BLX-alpha crossover, please refer to the following paper:

• Eshelman, L. and J. D. Schaffer. Real-Coded Genetic Algorithms and Interval-Schemata. FOGA (1992).

Parameters alpha (*float*) – Parametrizes blend operation.

Return type None

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Methods

crossover(parents_params, rng, study, ...)

Perform crossover of selected parent individuals.

Attributes

n_parents

crossover(parents_params, rng, study, search_space_bounds)

Perform crossover of selected parent individuals.

This method is called in *sample_relative()*.

Parameters

- parents_params (numpy.ndarray) A numpy.ndarray with dimensions num_parents x num_parameters. Represents a parameter space for each parent individual. This space is continuous for numerical parameters.
- rng (numpy.random.mtrand.RandomState) An instance of numpy.random. RandomState.
- study (optuna.study.study) Target study object.

Returns A 1-dimensional numpy.ndarray containing new parameter combination.

Return type numpy.ndarray

optuna.samplers.nsgaii.SPXCrossover

class optuna.samplers.nsgaii.SPXCrossover(epsilon=None)

A Simplex Crossover operation used by NSGAIISampler.

Uniformly samples child individuals from within a single simplex that is similar to the simplex produced by the parent individual. For further information about SPX crossover, please refer to the following paper:

 Shigeyoshi Tsutsui and Shigeyoshi Tsutsui and David E. Goldberg and David E. Goldberg and Kumara Sastry and Kumara Sastry Progress Toward Linkage Learning in Real-Coded GAs with Simplex Crossover. IlliGAL Report. 2000.

Parameters epsilon (Optional[float]) — Expansion rate. If not specified, defaults to sqrt(len(search_space) + 2).

Return type None

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Methods

crossover(parents_params, rng, study, ...)

Perform crossover of selected parent individuals.

Attributes

n_parents

crossover(parents_params, rng, study, search_space_bounds)

Perform crossover of selected parent individuals.

This method is called in sample_relative().

Parameters

- parents_params (numpy.ndarray) A numpy.ndarray with dimensions num_parents x num_parameters. Represents a parameter space for each parent individual. This space is continuous for numerical parameters.
- rng (numpy.random.mtrand.RandomState) An instance of numpy.random. RandomState.
- **study** (optuna.study.study) Target study object.

Returns A 1-dimensional numpy.ndarray containing new parameter combination.

Return type numpy.ndarray

optuna.samplers.nsgaii.SBXCrossover

class optuna.samplers.nsgaii.SBXCrossover(eta=None)

A Simulated Binary Crossover operation used by NSGAIISampler.

Generates a child from two parent individuals according to the polynomial probability distribution.

• Deb, K. and R. Agrawal. "Simulated Binary Crossover for Continuous Search Space." Complex Syst. 9 (1995): n. pag.

Parameters eta (Optional[float]) – Distribution index. A small value of eta allows distant solutions to be selected as children solutions. If not specified, takes default value of 2 for single objective functions and 20 for multi objective.

Return type None

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Methods

crossover(parents_params, rng, study, ...)

Perform crossover of selected parent individuals.

Attributes

n_parents

crossover(parents_params, rng, study, search_space_bounds)

Perform crossover of selected parent individuals.

This method is called in <code>sample_relative()</code>.

Parameters

- parents_params (numpy.ndarray) A numpy.ndarray with dimensions num_parents x num_parameters. Represents a parameter space for each parent individual. This space is continuous for numerical parameters.
- rng (numpy.random.mtrand.RandomState) An instance of numpy.random. RandomState.
- **study** (optuna.study.study) Target study object.

Returns A 1-dimensional numpy.ndarray containing new parameter combination.

Return type numpy.ndarray

optuna.samplers.nsgaii.VSBXCrossover

class optuna.samplers.nsgaii.VSBXCrossover(eta=None)

A modified Simulated Binary Crossover operation used by NSGAIISampler.

vSBX generates child individuals without excluding any region of the parameter space, while maintaining the excellent properties of SBX.

 Pedro J. Ballester, Jonathan N. Carter. Real-Parameter Genetic Algorithms for Finding Multiple Optimal Solutions in Multi-modal Optimization. GECCO 2003: 706-717

Parameters eta (Optional[float]) – Distribution index. A small value of eta allows distant solutions to be selected as children solutions. If not specified, takes default value of 2 for single objective functions and 20 for multi objective.

Return type None

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Methods

crossover(parents_params, rng, study, ...)

Perform crossover of selected parent individuals.

Attributes

n_parents

crossover(parents_params, rng, study, search_space_bounds)

Perform crossover of selected parent individuals.

This method is called in sample_relative().

Parameters

- parents_params (numpy.ndarray) A numpy.ndarray with dimensions num_parents x num_parameters. Represents a parameter space for each parent individual. This space is continuous for numerical parameters.
- rng (numpy.random.mtrand.RandomState) An instance of numpy.random. RandomState.
- **study** (optuna.study.study) Target study object.

Returns A 1-dimensional numpy.ndarray containing new parameter combination.

Return type numpy.ndarray

optuna.samplers.nsgaii.UNDXCrossover

class optuna.samplers.nsgaii.UNDXCrossover(sigma_xi=0.5, sigma_eta=None)

An Unimodal Normal Distribution Crossover used by NSGAIISampler.

Generates child individuals from the three parents using a multivariate normal distribution.

 H. Kita, I. Ono and S. Kobayashi, Multi-parental extension of the unimodal normal distribution crossover for real-coded genetic algorithms, Proceedings of the 1999 Congress on Evolutionary Computation-CEC99 (Cat. No. 99TH8406), 1999, pp. 1581-1588 Vol. 2

Parameters

- **sigma_xi** (*float*) Parametrizes normal distribution from which **xi** is drawn.
- **sigma_eta** (Optional[float]) Parametrizes normal distribution from which etas are drawn. If not specified, defaults to 0.35 / sqrt(len(search_space)).

Return type None

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Methods

crossover(parents_params, rng, study, ...)

Perform crossover of selected parent individuals.

Attributes

n_parents

crossover(parents_params, rng, study, search_space_bounds)

Perform crossover of selected parent individuals.

This method is called in sample_relative().

Parameters

- parents_params (numpy.ndarray) A numpy.ndarray with dimensions num_parents x num_parameters. Represents a parameter space for each parent individual. This space is continuous for numerical parameters.
- rng (numpy.random.mtrand.RandomState) An instance of numpy.random. RandomState.

- **study** (optuna.study.study) Target study object.
- search_space_bounds (numpy.ndarray) A numpy.ndarray with dimensions len_search_space x 2 representing numerical distribution bounds constructed from transformed search space.

Returns A 1-dimensional numpy.ndarray containing new parameter combination.

Return type numpy.ndarray

6.3.11 optuna.storages

The *storages* module defines a BaseStorage class which abstracts a backend database and provides library-internal interfaces to the read/write histories of the studies and trials. Library users who wish to use storage solutions other than the default in-memory storage should use one of the child classes of BaseStorage documented below.

optuna.storages.RDBStorage	Storage class for RDB backend.
optuna.storages.RedisStorage	Storage class for Redis backend.
optuna.storages.RetryFailedTrialCallback	Retry a failed trial up to a maximum number of times.
optuna.storages.fail_stale_trials	Fail stale trials and run their failure callbacks.

optuna.storages.RDBStorage

Storage class for RDB backend.

Note that library users can instantiate this class, but the attributes provided by this class are not supposed to be directly accessed by them.

Example

Create an *RDBStorage* instance with customized pool_size and timeout settings.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    return x**2

storage = optuna.storages.RDBStorage(
    url="sqlite:///:memory:",
    engine_kwargs={"pool_size": 20, "connect_args": {"timeout": 10}},
)

study = optuna.create_study(storage=storage)
study.optimize(objective, n_trials=10)
```

Parameters

- **url** (*str*) URL of the storage.
- engine_kwargs (Optional[Dict[str, Any]]) A dictionary of keyword arguments that is passed to sqlalchemy.engine.create engine function.
- **skip_compatibility_check** (*bool*) Flag to skip schema compatibility check if set to True.
- heartbeat_interval (Optional[int]) Interval to record the heartbeat. It is recorded every interval seconds.

Note: The heartbeat is supposed to be used with *optimize()*. If you use *ask()* and *tell()* instead, it will not work.

- **grace_period** (Optional [int]) Grace period before a running trial is failed from the last heartbeat. If it is None, the grace period will be 2 * heartbeat_interval.
- failed_trial_callback (Optional[Callable[[optuna.Study, optuna.trial._frozen.FrozenTrial], None]]) A callback function that is invoked after failing each stale trial. The function must accept two parameters with the following types in this order: Study and FrozenTrial.

Note: The procedure to fail existing stale trials is called just before asking the study for a new trial.

Return type None

Note: If you use MySQL, pool_pre_ping will be set to True by default to prevent connection timeout. You can turn it off with engine_kwargs['pool_pre_ping']=False, but it is recommended to keep the setting if execution time of your objective function is longer than the *wait_timeout* of your MySQL configuration.

Note: Mainly in a cluster environment, running trials are often killed unexpectedly. If you want to detect a failure of trials, please use the heartbeat mechanism. Set heartbeat_interval, grace_period, and failed_trial_callback appropriately according to your use case. For more details, please refer to the *tuto-rial* and Example page.

See also:

You can use RetryFailedTrialCallback to automatically retry failed trials detected by heartbeat.

Raises

- **ValueError** If the given *heartbeat_interval* or *grace_period* is not a positive integer.
- RuntimeError When a process tries to finish a trial that has already been set to FAIL by heartbeat.

Parameters

- url (str) -
- engine_kwargs (Optional[Dict[str, Any]]) -
- skip_compatibility_check(bool) -

- heartbeat_interval (Optional[int]) -
- grace_period(Optional[int]) -
- failed_trial_callback (Optional[Callable[[optuna.Study, optuna.trial._frozen.FrozenTrial], None]]) -

Return type None

Methods

<pre>check_trial_is_updatable(trial_id, trial_state)</pre>	Check whether a trial state is updatable.
<pre>create_new_study([study_name])</pre>	Create a new study from a name.
<pre>create_new_trial(study_id[, template_trial])</pre>	Create and add a new trial to a study.
<pre>delete_study(study_id)</pre>	Delete a study.
fail_stale_trials(study_id)	
<pre>get_all_study_summaries(include_best_trial)</pre>	Read a list of StudySummary objects.
<pre>get_all_trials(study_id[, deepcopy, states])</pre>	Read all trials in a study.
<pre>get_all_versions()</pre>	Return the schema version list.
<pre>get_best_trial(study_id)</pre>	Return the trial with the best value in a study.
<pre>get_current_version()</pre>	Return the schema version currently used by this stor-
	age.
<pre>get_failed_trial_callback()</pre>	Get the failed trial callback function.
<pre>get_head_version()</pre>	Return the latest schema version.
<pre>get_heartbeat_interval()</pre>	Get the heartbeat interval if it is set.
<pre>get_n_trials(study_id[, state])</pre>	Count the number of trials in a study.
<pre>get_study_directions(study_id)</pre>	Read whether a study maximizes or minimizes an ob-
	jective.
<pre>get_study_id_from_name(study_name)</pre>	Read the ID of a study.
<pre>get_study_id_from_trial_id(trial_id)</pre>	Read the ID of a study to which a trial belongs.
<pre>get_study_name_from_id(study_id)</pre>	Read the study name of a study.
<pre>get_study_system_attrs(study_id)</pre>	Read the optuna-internal attributes of a study.
<pre>get_study_user_attrs(study_id)</pre>	Read the user-defined attributes of a study.
get_trial(trial_id)	Read a trial.
<pre>get_trial_id_from_study_id_trial_number(</pre>	•
<pre>get_trial_number_from_id(trial_id)</pre>	Read the trial number of a trial.
<pre>get_trial_param(trial_id, param_name)</pre>	Read the parameter of a trial.
<pre>get_trial_params(trial_id)</pre>	Read the parameter dictionary of a trial.
<pre>get_trial_system_attrs(trial_id)</pre>	Read the optuna-internal attributes of a trial.
<pre>get_trial_user_attrs(trial_id)</pre>	Read the user-defined attributes of a trial.
is_heartbeat_enabled()	Check whether the storage enables the heartbeat.
<pre>read_trials_from_remote_storage(study_id)</pre>	Make an internal cache of trials up-to-date.
record_heartbeat(trial_id)	Record the heartbeat of the trial.
remove_session()	Removes the current session.
<pre>set_study_directions(study_id, directions)</pre>	Register optimization problem directions to a study.
<pre>set_study_system_attr(study_id, key, value)</pre>	Register an optuna-internal attribute to a study.
<pre>set_study_user_attr(study_id, key, value)</pre>	Register a user-defined attribute to a study.
<pre>set_trial_intermediate_value(trial_id, step,</pre>	Report an intermediate value of an objective func-
)	tion.
<pre>set_trial_param(trial_id, param_name,)</pre>	Set a parameter to a trial.
	continues on post nage

continues on next page

Table 1 – continued from previous page

rabio i continuou nom provious pago	
set_trial_state(trial_id, state)	
set_trial_state_values(trial_id, state[, values])	Update the state and values of a trial.
set_trial_system_attr(trial_id, key, value)	Set an optuna-internal attribute to a trial.
set_trial_user_attr(trial_id, key, value)	Set a user-defined attribute to a trial.
set_trial_values(trial_id, values)	
upgrade()	Upgrade the storage schema.

check_trial_is_updatable(trial_id, trial_state)

Check whether a trial state is updatable.

Parameters

- **trial_id** (*int*) ID of the trial. Only used for an error message.
- trial_state (optuna.trial._state.TrialState) Trial state to check.

Raises RuntimeError – If the trial is already finished.

Return type None

create_new_study(study name=None)

Create a new study from a name.

If no name is specified, the storage class generates a name. The returned study ID is unique among all current and deleted studies.

 $\label{eq:parameters} \textbf{Parameters study_name} \ (\textit{Optional[str]}) - Name \ of \ the \ new \ study \ to \ create.$

Returns ID of the created study.

Raises optuma.exceptions.DuplicatedStudyError — If a study with the same study_name already exists.

Return type int

create_new_trial(study_id, template_trial=None)

Create and add a new trial to a study.

The returned trial ID is unique among all current and deleted trials.

Parameters

- **study_id** (*int*) ID of the study.
- template_trial (Optional[optuna.trial._frozen.FrozenTrial]) Template FronzenTrial with default user-attributes, system-attributes, intermediate-values, and a state.

Returns ID of the created trial.

Raises KeyError – If no study with the matching study_id exists.

Return type int

delete_study(study_id)

Delete a study.

Parameters study_id (int) – ID of the study.

Raises KeyError – If no study with the matching study_id exists.

Return type None

```
fail_stale_trials(study_id)
```

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v5.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use fail_stale_trials() instead.

```
Parameters study_id (int) -
```

Return type *List*[int]

get_all_study_summaries(include_best_trial)

Read a list of StudySummary objects.

Parameters include_best_trial (*bool*) – If True, *StudySummary* objects have the best trials in the best_trial attribute. Otherwise, best_trial is None.

Returns A list of StudySummary objects.

Return type *List*[*optuna.study*._*study*_*summary*.*StudySummary*]

get_all_trials(study_id, deepcopy=True, states=None)

Read all trials in a study.

Parameters

- **study_id** (*int*) ID of the study.
- **deepcopy** (*boo1*) Whether to copy the list of trials before returning. Set to True if you intend to update the list or elements of the list.
- **states** (Optional[Container[optuna.trial._state.TrialState]]) Trial states to filter on. If None, include all states.

Returns List of trials in the study.

Raises KeyError – If no study with the matching study_id exists.

Return type *List[optuna.trial._frozen.FrozenTrial]*

get_all_versions()

Return the schema version list.

Return type *List*[str]

```
get_best_trial(study id)
```

Return the trial with the best value in a study.

This method is valid only during single-objective optimization.

Parameters study_id (int) – ID of the study.

Returns The trial with the best objective value among all finished trials in the study.

Raises

- **KeyError** If no study with the matching study_id exists.
- **RuntimeError** If the study has more than one direction.

• **ValueError** – If no trials have been completed.

Return type optuna.trial._frozen.FrozenTrial

get_current_version()

Return the schema version currently used by this storage.

Return type str

get_failed_trial_callback()

Get the failed trial callback function.

Returns The failed trial callback function if it is set, otherwise None.

Return type Optional[Callable[[optuna.study.study, optuna.trial._frozen.FrozenTrial], None]]

get_head_version()

Return the latest schema version.

Return type str

get_heartbeat_interval()

Get the heartbeat interval if it is set.

Returns The heartbeat interval if it is set, otherwise None.

Return type *Optional*[int]

get_n_trials(study_id, state=None)

Count the number of trials in a study.

Parameters

- **study_id** (*int*) ID of the study.
- **state** (Optional[Union[Tuple[optuna.trial._state.TrialState, ...], optuna.trial._state.TrialState]]) Trial states to filter on. If None, include all states.

Returns Number of trials in the study.

Raises KeyError – If no study with the matching study_id exists.

Return type int

get_study_directions(study id)

Read whether a study maximizes or minimizes an objective.

Parameters study_id (int) – ID of a study.

Returns Optimization directions list of the study.

Raises KeyError – If no study with the matching study_id exists.

Return type *List*[optuna.study._study_direction.StudyDirection]

get_study_id_from_name(study_name)

Read the ID of a study.

Parameters study_name (str) – Name of the study.

Returns ID of the study.

Raises KeyError – If no study with the matching study_name exists.

```
Return type int
get_study_id_from_trial_id(trial_id)
     Read the ID of a study to which a trial belongs.
         Parameters trial_id (int) – ID of the trial.
         Returns ID of the study.
         Raises KeyError – If no trial with the matching trial_id exists.
         Return type int
get_study_name_from_id(study_id)
     Read the study name of a study.
         Parameters study_id (int) – ID of the study.
         Returns Name of the study.
         Raises KeyError – If no study with the matching study_id exists.
         Return type str
get_study_system_attrs(study id)
     Read the optuna-internal attributes of a study.
         Parameters study_id (int) – ID of the study.
         Returns Dictionary with the optuna-internal attributes of the study.
         Raises KeyError – If no study with the matching study_id exists.
         Return type Dict[str, Any]
get_study_user_attrs(study_id)
     Read the user-defined attributes of a study.
         Parameters study_id (int) – ID of the study.
         Returns Dictionary with the user attributes of the study.
         Raises KeyError – If no study with the matching study_id exists.
         Return type Dict[str, Any]
get_trial(trial id)
     Read a trial.
         Parameters trial_id (int) – ID of the trial.
         Returns Trial with a matching trial ID.
         Raises KeyError – If no trial with the matching trial_id exists.
         Return type optuna.trial._frozen.FrozenTrial
get_trial_id_from_study_id_trial_number(study_id, trial_number)
     Read the trial ID of a trial.
         Parameters
              • study_id (int) – ID of the study.
              • trial_number (int) – Number of the trial.
```

Returns ID of the trial.

```
Raises KeyError – If no trial with the matching study_id and trial_number exists.
         Return type int
get_trial_number_from_id(trial_id)
     Read the trial number of a trial.
     Note: The trial number is only unique within a study, and is sequential.
         Parameters trial_id (int) – ID of the trial.
         Returns Number of the trial.
         Raises KeyError – If no trial with the matching trial_id exists.
         Return type int
get_trial_param(trial_id, param_name)
     Read the parameter of a trial.
         Parameters
              • trial_id (int) – ID of the trial.
              • param_name (str) – Name of the parameter.
         Returns Internal representation of the parameter.
         Raises KeyError – If no trial with the matching trial_id exists. If no such parameter exists.
         Return type float
get_trial_params(trial_id)
     Read the parameter dictionary of a trial.
         Parameters trial_id (int) – ID of the trial.
             tations of the parameter values.
```

Returns Dictionary of a parameters. Keys are parameter names and values are internal represen-

Raises KeyError – If no trial with the matching trial_id exists.

Return type *Dict*[str, *Any*]

```
get_trial_system_attrs(trial id)
```

Read the optuna-internal attributes of a trial.

Parameters trial_id (*int*) – ID of the trial.

Returns Dictionary with the optuna-internal attributes of the trial.

Raises KeyError – If no trial with the matching trial_id exists.

Return type *Dict*[str, *Any*]

get_trial_user_attrs(trial_id)

Read the user-defined attributes of a trial.

Parameters trial_id (*int*) – ID of the trial.

Returns Dictionary with the user-defined attributes of the trial.

Raises KeyError – If no trial with the matching trial_id exists.

```
Return type Dict[str, Any]
```

is_heartbeat_enabled()

Check whether the storage enables the heartbeat.

Returns True if the storage supports the heartbeat and the return value of get_heartbeat_interval() is an integer, otherwise False.

Return type bool

read_trials_from_remote_storage(study id)

Make an internal cache of trials up-to-date.

Parameters study_id (int) – ID of the study.

Raises KeyError – If no study with the matching study_id exists.

Return type None

record_heartbeat(trial_id)

Record the heartbeat of the trial.

Parameters trial_id (*int*) – ID of the trial.

Return type None

remove_session()

Removes the current session.

A session is stored in SQLAlchemy's ThreadLocalRegistry for each thread. This method closes and removes the session which is associated to the current thread. Particularly, under multi-thread use cases, it is important to call this method *from each thread*. Otherwise, all sessions and their associated DB connections are destructed by a thread that occasionally invoked the garbage collector. By default, it is not allowed to touch a SQLite connection from threads other than the thread that created the connection. Therefore, we need to explicitly close the connection from each thread.

Return type None

set_study_directions(study_id, directions)

Register optimization problem directions to a study.

Parameters

- **study_id** (*int*) ID of the study.
- **directions** (Sequence[optuna.study._study_direction.StudyDirection]) A sequence of direction whose element is either MAXIMIZE or MINIMIZE.

Raises

- **KeyError** If no study with the matching study_id exists.
- ValueError If the directions are already set and the each coordinate of passed directions is the opposite direction or NOT_SET.

Return type None

set_study_system_attr(study_id, key, value)

Register an optuna-internal attribute to a study.

This method overwrites any existing attribute.

Parameters

• **study_id** (*int*) – ID of the study.

- **key** (*str*) Attribute key.
- value (*Any*) Attribute value. It should be JSON serializable.

Raises KeyError – If no study with the matching study_id exists.

Return type None

set_study_user_attr(study id, key, value)

Register a user-defined attribute to a study.

This method overwrites any existing attribute.

Parameters

- **study_id** (*int*) ID of the study.
- **key** (*str*) Attribute key.
- **value** (*Any*) Attribute value. It should be JSON serializable.

Raises KeyError – If no study with the matching study_id exists.

Return type None

set_trial_intermediate_value(trial_id, step, intermediate_value)

Report an intermediate value of an objective function.

This method overwrites any existing intermediate value associated with the given step.

Parameters

- **trial_id** (*int*) ID of the trial.
- **step** (*int*) Step of the trial (e.g., the epoch when training a neural network).
- intermediate_value (float) Intermediate value corresponding to the step.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- RuntimeError If the trial is already finished.

Return type None

set_trial_param(trial_id, param_name, param_value_internal, distribution)

Set a parameter to a trial.

Parameters

- **trial_id** (*int*) ID of the trial.
- param_name (str) Name of the parameter.
- param_value_internal (float) Internal representation of the parameter value.
- **distribution** (optuna.distributions.BaseDistribution) Sampled distribution of the parameter.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- **RuntimeError** If the trial is already finished.

Return type None

set_trial_state(trial_id, state)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v5.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use set_trial_state_values() instead.

Parameters

- trial_id(int)-
- state (optuma.trial._state.TrialState) -

Return type bool

set_trial_state_values(trial_id, state, values=None)

Update the state and values of a trial.

Set return values of an objective function to values argument. If values argument is not None, this method overwrites any existing trial values.

Parameters

- trial_id (int) ID of the trial.
- **state** (optuna.trial._state.TrialState) New state of the trial.
- values (Optional [Sequence [float]]) Values of the objective function.

Returns True if the state is successfully updated. False if the state is kept the same. The latter happens when this method tries to update the state of *RUNNING* trial to *RUNNING*.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- **RuntimeError** If the trial is already finished.

Return type bool

set_trial_system_attr(trial id, key, value)

Set an optuna-internal attribute to a trial.

This method overwrites any existing attribute.

Parameters

- trial_id (int) ID of the trial.
- **key** (*str*) Attribute key.
- **value** (*Any*) Attribute value. It should be JSON serializable.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- RuntimeError If the trial is already finished.

Return type None

set_trial_user_attr(trial_id, key, value)

Set a user-defined attribute to a trial.

This method overwrites any existing attribute.

Parameters

- trial_id (int) ID of the trial.
- **key** (*str*) Attribute key.
- **value** (*Any*) Attribute value. It should be JSON serializable.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- RuntimeError If the trial is already finished.

Return type None

set_trial_values(trial_id, values)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v5.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use set_trial_state_values() instead.

Parameters

- trial_id(int)-
- values (Sequence[float]) -

Return type None

upgrade()

Upgrade the storage schema.

Return type None

optuna.storages.RedisStorage

Storage class for Redis backend.

Note that library users can instantiate this class, but the attributes provided by this class are not supposed to be directly accessed by them.

We create an RedisStorage instance using the given redis database URL.

```
import optuna

def objective(trial):
    ...

storage = optuna.storages.RedisStorage(
    url="redis://passwd@localhost:port/db",
)

study = optuna.create_study(storage=storage)
study.optimize(objective)
```

Parameters

- **url** (*str*) URL of the redis storage, password and db are optional. (ie: redis://localhost:6379)
- heartbeat_interval (Optional[int]) Interval to record the heartbeat. It is recorded every interval seconds.

Note: The heartbeat is supposed to be used with *optimize()*. If you use *ask()* and *tell()* instead, it will not work.

- **grace_period** (*Optional[int]*) Grace period before a running trial is failed from the last heartbeat. If it is None, the grace period will be 2 * *heartbeat_interval*.
- failed_trial_callback (Optional[Callable[[optuna.Study, optuna.trial._frozen.FrozenTrial], None]]) A callback function that is invoked after failing each stale trial. The function must accept two parameters with the following types in this order: Study and FrozenTrial.

Note: The procedure to fail existing stale trials is called just before asking the study for a new trial.

Return type None

Note: If you use plan to use Redis as a storage mechanism for optuna, make sure Redis in installed and running. Please execute \$ pip install -U redis to install redis python library.

Raises ValueError – If the given *heartbeat_interval* or *grace_period* is not a positive integer.

Parameters

- url (str) -
- heartbeat_interval (Optional[int]) -

- grace_period(Optional[int]) -
- failed_trial_callback (Optional[Callable[[optuna.Study, optuna.trial._frozen.FrozenTrial], None]]) -

Return type None

Note: Added in v1.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v1.4.0.

Methods

<pre>check_trial_is_updatable(trial_id, trial_state)</pre>	Check whether a trial state is updatable.
<pre>create_new_study([study_name])</pre>	Create a new study from a name.
<pre>create_new_trial(study_id[, template_trial])</pre>	Create and add a new trial to a study.
delete_study(study_id)	Delete a study.
fail_stale_trials(study_id)	
<pre>get_all_study_summaries(include_best_trial)</pre>	Read a list of StudySummary objects.
<pre>get_all_trials(study_id[, deepcopy, states])</pre>	Read all trials in a study.
<pre>get_best_trial(study_id)</pre>	Return the trial with the best value in a study.
<pre>get_failed_trial_callback()</pre>	Get the failed trial callback function.
<pre>get_heartbeat_interval()</pre>	Get the heartbeat interval if it is set.
<pre>get_n_trials(study_id[, state])</pre>	Count the number of trials in a study.
<pre>get_study_directions(study_id)</pre>	Read whether a study maximizes or minimizes an ob-
	jective.
<pre>get_study_id_from_name(study_name)</pre>	Read the ID of a study.
<pre>get_study_id_from_trial_id(trial_id)</pre>	Read the ID of a study to which a trial belongs.
<pre>get_study_name_from_id(study_id)</pre>	Read the study name of a study.
<pre>get_study_system_attrs(study_id)</pre>	Read the optuna-internal attributes of a study.
<pre>get_study_user_attrs(study_id)</pre>	Read the user-defined attributes of a study.
<pre>get_trial(trial_id)</pre>	Read a trial.
<pre>get_trial_id_from_study_id_trial_number(</pre>	
<pre>get_trial_number_from_id(trial_id)</pre>	Read the trial number of a trial.
<pre>get_trial_param(trial_id, param_name)</pre>	Read the parameter of a trial.
<pre>get_trial_params(trial_id)</pre>	Read the parameter dictionary of a trial.
<pre>get_trial_system_attrs(trial_id)</pre>	Read the optuna-internal attributes of a trial.
<pre>get_trial_user_attrs(trial_id)</pre>	Read the user-defined attributes of a trial.
is_heartbeat_enabled()	Check whether the storage enables the heartbeat.
read_trials_from_remote_storage(study_id)	Make an internal cache of trials up-to-date.
record_heartbeat(trial_id)	Record the heartbeat of the trial.
remove_session()	Clean up all connections to a database.
set_study_directions(study_id, directions)	Register optimization problem directions to a study.
<pre>set_study_system_attr(study_id, key, value)</pre>	Register an optuna-internal attribute to a study.
set_study_user_attr(study_id, key, value)	Register a user-defined attribute to a study.
<pre>set_trial_intermediate_value(trial_id, step,</pre>	Report an intermediate value of an objective func-
)	tion.
<pre>set_trial_param(trial_id, param_name,)</pre>	Set a parameter to a trial.
	continues on next page

continues on next page

Table 2 – continued from previous page

	1 0
set_trial_state(trial_id, state)	
<pre>set_trial_state_values(trial_id, state[, val-</pre>	Undate the state and values of a trial
, — · -	opadie the state and varies of a trial.
ues])	
	Cat an antona internal attribute to a trial
<pre>set_trial_system_attr(trial_id, key, value)</pre>	Set an optuna-internal attribute to a trial.
set_trial_user_attr(trial_id, key, value)	Set a user-defined attribute to a trial.
See_errar_user_acer (trial_id, key, value)	Set a user defined attribute to a trial.
set_trial_values(trial_id, values)	
5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5 5	

check_trial_is_updatable(trial_id, trial_state)

Check whether a trial state is updatable.

Parameters

- **trial_id** (*int*) ID of the trial. Only used for an error message.
- trial_state (optuna.trial._state.TrialState) Trial state to check.

Raises RuntimeError – If the trial is already finished.

Return type None

create_new_study(study_name=None)

Create a new study from a name.

If no name is specified, the storage class generates a name. The returned study ID is unique among all current and deleted studies.

Parameters study_name (Optional[str]) – Name of the new study to create.

Returns ID of the created study.

Raises optuma.exceptions.DuplicatedStudyError — If a study with the same study_name already exists.

Return type int

create_new_trial(study_id, template_trial=None)

Create and add a new trial to a study.

The returned trial ID is unique among all current and deleted trials.

Parameters

- **study_id** (*int*) ID of the study.
- template_trial (Optional[optuna.trial._frozen.FrozenTrial]) Template FronzenTrial with default user-attributes, system-attributes, intermediate-values, and a state.

Returns ID of the created trial.

Raises KeyError – If no study with the matching study_id exists.

Return type int

delete_study(study_id)

Delete a study.

Parameters study_id (int) – ID of the study.

Raises KeyError – If no study with the matching study_id exists.

Return type None

fail_stale_trials(study_id)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v5.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use fail_stale_trials() instead.

```
Parameters study_id (int) -
```

Return type *List*[int]

get_all_study_summaries(include_best_trial)

Read a list of StudySummary objects.

Parameters include_best_trial (*bool*) – If True, *StudySummary* objects have the best trials in the best_trial attribute. Otherwise, best_trial is None.

Returns A list of *StudySummary* objects.

Return type *List*[optuna.study._study_summary.StudySummary]

```
get_all_trials(study_id, deepcopy=True, states=None)
```

Read all trials in a study.

Parameters

- **study_id** (*int*) ID of the study.
- **deepcopy** (*boo1*) Whether to copy the list of trials before returning. Set to True if you intend to update the list or elements of the list.
- **states** (Optional[Container[optuna.trial._state.TrialState]]) Trial states to filter on. If None, include all states.

Returns List of trials in the study.

Raises KeyError – If no study with the matching study_id exists.

Return type *List[optuna.trial._frozen.FrozenTrial]*

```
get_best_trial(study_id)
```

Return the trial with the best value in a study.

This method is valid only during single-objective optimization.

Parameters $study_id(int) - ID of the study.$

Returns The trial with the best objective value among all finished trials in the study.

Raises

- **KeyError** If no study with the matching study_id exists.
- RuntimeError If the study has more than one direction.
- ValueError If no trials have been completed.

Return type optuna.trial._frozen.FrozenTrial

```
get_failed_trial_callback()

Get the failed trial callback function.
```

Returns The failed trial callback function if it is set, otherwise None.

Return type Optional[Callable[[optuna.study.study, optuna.trial._frozen.FrozenTrial], None]]

```
get_heartbeat_interval()
```

Get the heartbeat interval if it is set.

Returns The heartbeat interval if it is set, otherwise None.

Return type *Optional*[int]

```
get_n_trials(study_id, state=None)
```

Count the number of trials in a study.

Parameters

- **study_id** (*int*) ID of the study.
- **state** (Optional[Union[Tuple[optuna.trial._state.TrialState, ...], optuna.trial._state.TrialState]]) Trial states to filter on. If None, include all states.

Returns Number of trials in the study.

Raises KeyError – If no study with the matching study_id exists.

Return type int

get_study_directions(study_id)

Read whether a study maximizes or minimizes an objective.

Parameters study_id (int) – ID of a study.

Returns Optimization directions list of the study.

Raises KeyError – If no study with the matching study_id exists.

Return type *List*[optuna.study._study_direction.StudyDirection]

get_study_id_from_name(study_name)

Read the ID of a study.

Parameters study_name (str) – Name of the study.

Returns ID of the study.

Raises KeyError – If no study with the matching study_name exists.

Return type int

get_study_id_from_trial_id(trial id)

Read the ID of a study to which a trial belongs.

Parameters trial_id (*int*) – ID of the trial.

Returns ID of the study.

Raises KeyError – If no trial with the matching trial_id exists.

Return type int

```
get_study_name_from_id(study_id)
     Read the study name of a study.
         Parameters study_id (int) – ID of the study.
         Returns Name of the study.
         Raises KeyError – If no study with the matching study_id exists.
         Return type str
get_study_system_attrs(study_id)
     Read the optuna-internal attributes of a study.
         Parameters study_id (int) – ID of the study.
         Returns Dictionary with the optuna-internal attributes of the study.
         Raises KeyError – If no study with the matching study_id exists.
         Return type Dict[str, Any]
get_study_user_attrs(study_id)
     Read the user-defined attributes of a study.
         Parameters study_id (int) – ID of the study.
         Returns Dictionary with the user attributes of the study.
         Raises KeyError – If no study with the matching study_id exists.
         Return type Dict[str, Any]
get_trial(trial_id)
     Read a trial.
         Parameters trial_id (int) – ID of the trial.
         Returns Trial with a matching trial ID.
         Raises KeyError – If no trial with the matching trial_id exists.
         Return type optuna.trial._frozen.FrozenTrial
get_trial_id_from_study_id_trial_number(study id, trial number)
     Read the trial ID of a trial.
         Parameters
              • study_id (int) – ID of the study.
              • trial_number (int) – Number of the trial.
         Returns ID of the trial.
         Raises KeyError – If no trial with the matching study_id and trial_number exists.
         Return type int
get_trial_number_from_id(trial id)
     Read the trial number of a trial.
     Note: The trial number is only unique within a study, and is sequential.
```

Parameters trial_id (*int*) – ID of the trial.

```
Returns Number of the trial.
```

Raises KeyError – If no trial with the matching trial_id exists.

Return type int

get_trial_param(trial_id, param_name)

Read the parameter of a trial.

Parameters

- trial_id (int) ID of the trial.
- param_name (str) Name of the parameter.

Returns Internal representation of the parameter.

Raises KeyError – If no trial with the matching trial_id exists. If no such parameter exists.

Return type float

```
get_trial_params(trial_id)
```

Read the parameter dictionary of a trial.

```
Parameters trial_id (int) – ID of the trial.
```

Returns Dictionary of a parameters. Keys are parameter names and values are internal representations of the parameter values.

Raises KeyError – If no trial with the matching trial_id exists.

Return type *Dict*[str, *Any*]

```
get_trial_system_attrs(trial_id)
```

Read the optuna-internal attributes of a trial.

```
Parameters trial_id (int) – ID of the trial.
```

Returns Dictionary with the optuna-internal attributes of the trial.

Raises KeyError – If no trial with the matching trial_id exists.

Return type *Dict*[str, *Any*]

```
get_trial_user_attrs(trial_id)
```

Read the user-defined attributes of a trial.

```
Parameters trial_id (int) – ID of the trial.
```

Returns Dictionary with the user-defined attributes of the trial.

Raises KeyError – If no trial with the matching trial_id exists.

Return type *Dict*[str, *Any*]

is_heartbeat_enabled()

Check whether the storage enables the heartbeat.

Returns True if the storage supports the heartbeat and the return value of get_heartbeat_interval() is an integer, otherwise False.

Return type bool

read_trials_from_remote_storage(study_id)

Make an internal cache of trials up-to-date.

Parameters study_id (int) – ID of the study.

Raises KeyError – If no study with the matching study_id exists.

Return type None

record_heartbeat(trial_id)

Record the heartbeat of the trial.

Parameters trial_id (*int*) – ID of the trial.

Return type None

remove_session()

Clean up all connections to a database.

Return type None

set_study_directions(study_id, directions)

Register optimization problem directions to a study.

Parameters

- **study_id** (*int*) ID of the study.
- **directions** (Sequence[optuna.study._study_direction.StudyDirection]) A sequence of direction whose element is either MAXIMIZE or MINIMIZE.

Raises

- **KeyError** If no study with the matching study_id exists.
- ValueError If the directions are already set and the each coordinate of passed directions is the opposite direction or NOT_SET.

Return type None

set_study_system_attr(study_id, key, value)

Register an optuna-internal attribute to a study.

This method overwrites any existing attribute.

Parameters

- **study_id** (*int*) ID of the study.
- **key** (*str*) Attribute key.
- value (*Any*) Attribute value. It should be JSON serializable.

Raises KeyError – If no study with the matching study_id exists.

Return type None

set_study_user_attr(study_id, key, value)

Register a user-defined attribute to a study.

This method overwrites any existing attribute.

Parameters

- **study_id** (*int*) ID of the study.
- **key** (*str*) Attribute key.

• **value** (*Any*) – Attribute value. It should be JSON serializable.

Raises KeyError – If no study with the matching study_id exists.

Return type None

set_trial_intermediate_value(trial_id, step, intermediate_value)

Report an intermediate value of an objective function.

This method overwrites any existing intermediate value associated with the given step.

Parameters

- trial_id (int) ID of the trial.
- **step** (*int*) Step of the trial (e.g., the epoch when training a neural network).
- intermediate_value (float) Intermediate value corresponding to the step.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- RuntimeError If the trial is already finished.

Return type None

set_trial_param(trial id, param name, param value internal, distribution)

Set a parameter to a trial.

Parameters

- **trial_id** (*int*) ID of the trial.
- param_name (str) Name of the parameter.
- param_value_internal (float) Internal representation of the parameter value.
- $\hbox{\bf distribution} \ (optuna. \ distributions. Base Distribution) Sampled \ distribution \ of the parameter.$

Raises

- **KeyError** If no trial with the matching trial_id exists.
- **RuntimeError** If the trial is already finished.

Return type None

```
set_trial_state(trial_id, state)
```

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v5.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use set_trial_state_values() instead.

Parameters

- trial_id(int)-
- state (optuna.trial._state.TrialState) -

Return type bool

set_trial_state_values(trial_id, state, values=None)

Update the state and values of a trial.

Set return values of an objective function to values argument. If values argument is not None, this method overwrites any existing trial values.

Parameters

- trial_id (int) ID of the trial.
- **state** (optuna.trial._state.TrialState) New state of the trial.
- values (Optional [Sequence [float]]) Values of the objective function.

Returns True if the state is successfully updated. False if the state is kept the same. The latter happens when this method tries to update the state of *RUNNING* trial to *RUNNING*.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- RuntimeError If the trial is already finished.

Return type bool

set_trial_system_attr(trial_id, key, value)

Set an optuna-internal attribute to a trial.

This method overwrites any existing attribute.

Parameters

- trial_id (int) ID of the trial.
- **key** (*str*) Attribute key.
- **value** (*Any*) Attribute value. It should be JSON serializable.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- RuntimeError If the trial is already finished.

Return type None

set_trial_user_attr(trial id, key, value)

Set a user-defined attribute to a trial.

This method overwrites any existing attribute.

Parameters

- **trial_id** (*int*) ID of the trial.
- **key** (*str*) Attribute key.
- value (Any) Attribute value. It should be JSON serializable.

Raises

- **KeyError** If no trial with the matching trial_id exists.
- **RuntimeError** If the trial is already finished.

Return type None

```
set_trial_values(trial id, values)
```

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v5.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use set_trial_state_values() instead.

Parameters

- trial_id(int)-
- values (Sequence[float]) -

Return type None

optuna.storages.RetryFailedTrialCallback

class optuna.storages.**RetryFailedTrialCallback**($max_retry=None$, $inherit_intermediate_values=False$)

Retry a failed trial up to a maximum number of times.

When a trial fails, this callback can be used with the optuna.storage class to recreate the trial in TrialState. WAITING to queue up the trial to be run again.

The failed trial can be identified by the <code>retried_trial_number()</code> function. Even if repetitive failure occurs (a retried trial fails again), this method returns the number of the original trial. To get a full list including the numbers of the retried trials as well as their original trial, call the <code>retry_history()</code> function.

This callback is helpful in environments where trials may fail due to external conditions, such as being preempted by other processes.

Usage:

```
import optuna
from optuna.storages import RetryFailedTrialCallback

storage = optuna.storages.RDBStorage(
    url="sqlite:///:memory:",
    heartbeat_interval=60,
    grace_period=120,
    failed_trial_callback=RetryFailedTrialCallback(max_retry=3),
)

study = optuna.create_study(
    storage=storage,
)
```

See also:

See RDBStorage.

Parameters

• max_retry (Optional[int]) - The max number of times a trial can be retried. Must be set to None or an integer. If set to the default value of None will retry indefinitely. If set to an integer, will only retry that many times.

• inherit_intermediate_values (bool) — Option to inherit *trial.intermediate_values* reported by *optuna.trial.Trial.report()* from the failed trial. Default is False.

Return type None

Note: Added in v2.8.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.8.0.

Methods

retried_trial_number(trial)	Return the number of the original trial being retried.
retry_history(trial)	Return the list of retried trial numbers with respect to
	the specified trial.

static retried_trial_number(trial)

Return the number of the original trial being retried.

Parameters trial (optuna.trial._frozen.FrozenTrial) - The trial object.

Returns The number of the first failed trial. If not retry of a previous trial, returns None.

Return type *Optional*[int]

Note: Added in v2.8.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.8.0.

static retry_history(trial)

Return the list of retried trial numbers with respect to the specified trial.

Parameters trial (optuna.trial._frozen.FrozenTrial) - The trial object.

Returns A list of trial numbers in ascending order of the series of retried trials. The first item of the list indicates the original trial which is identical to the <code>retried_trial_number()</code>, and the last item is the one right before the specified trial in the retry series. If the specified trial is not a retry of any trial, returns an empty list.

Return type *List*[int]

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

optuna.storages.fail stale trials

optuna.storages.fail_stale_trials(study)

Fail stale trials and run their failure callbacks.

The running trials whose heartbeat has not been updated for a long time will be failed, that is, those states will be changed to FAIL.

See also:

See RDBStorage.

Parameters study (optuna.study.study) - Study holding the trials to check.

Return type None

Note: Added in v2.9.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.9.0.

6.3.12 optuna.study

The *study* module implements the *Study* object and related functions. A public constructor is available for the *Study* class, but direct use of this constructor is not recommended. Instead, library users should create and load a *Study* using *create_study()* and *load_study()* respectively.

optuna.study.Study	A study corresponds to an optimization task, i.e., a set
	of trials.
optuna.study.create_study	Create a new Study.
optuna.study.load_study	Load the existing <i>Study</i> that has the specified name.
optuna.study.delete_study	Delete a Study object.
optuna.study.copy_study	Copy study from one storage to another.
optuna.study.get_all_study_summaries	Get all history of studies stored in a specified storage.
optuna.study.MaxTrialsCallback	Set a maximum number of trials before ending the study.
optuna.study.StudyDirection	Direction of a Study.
optuna.study.StudySummary	Basic attributes and aggregated results of a <i>Study</i> .

optuna.study.Study

class optuna.study.Study(study_name, storage, sampler=None, pruner=None)

A study corresponds to an optimization task, i.e., a set of trials.

This object provides interfaces to run a new *Trial*, access trials' history, set/get user-defined attributes of the study itself.

Note that the direct use of this constructor is not recommended. To create and load a study, please refer to the documentation of *create_study()* and *load_study()* respectively.

Methods

add_trial(trial)	Add trial to study.
add_trials(trials)	Add trials to study.
ask([fixed_distributions])	Create a new trial from which hyperparameters can
	be suggested.
<pre>enqueue_trial(params[, user_attrs])</pre>	Enqueue a trial with given parameter values.
<pre>get_trials([deepcopy, states])</pre>	Return all trials in the study.
<pre>optimize(func[, n_trials, timeout, n_jobs,])</pre>	Optimize an objective function.
set_system_attr(key, value)	Set a system attribute to the study.
set_user_attr(key, value)	Set a user attribute to the study.
stop()	Exit from the current optimization loop after the run-
	ning trials finish.
tell(trial[, values, state, skip_if_finished])	Finish a trial created with ask().
trials_dataframe([attrs, multi_index])	Export trials as a pandas DataFrame.

Attributes

best_params	Return parameters of the best trial in the study.
best_trial	Return the best trial in the study.
best_trials	Return trials located at the Pareto front in the study.
best_value	Return the best objective value in the study.
direction	Return the direction of the study.
directions	Return the directions of the study.
system_attrs	Return system attributes.
trials	Return all trials in the study.
user_attrs	Return user attributes.

Parameters

- $study_name(str)$ –
- **storage** (Union[str, optuna.storages._base.BaseStorage]) -
- **sampler** (Optional[samplers.BaseSampler]) -
- pruner (Optional[optuna.pruners._base.BasePruner]) -

Return type None

add_trial(trial)

Add trial to study.

The trial is validated before being added.

```
import optuna
from optuna.distributions import FloatDistribution
def objective(trial):
   x = trial.suggest_float("x", 0, 10)
   return x**2
study = optuna.create_study()
assert len(study.trials) == 0
trial = optuna.trial.create_trial(
   params = {"x": 2.0},
    distributions={"x": FloatDistribution(0, 10)},
    value=4.0,
)
study.add_trial(trial)
assert len(study.trials) == 1
study.optimize(objective, n_trials=3)
assert len(study.trials) == 4
other_study = optuna.create_study()
for trial in study.trials:
    other_study.add_trial(trial)
assert len(other_study.trials) == len(study.trials)
other_study.optimize(objective, n_trials=2)
assert len(other_study.trials) == len(study.trials) + 2
```

See also:

This method should in general be used to add already evaluated trials (trial.state.is_finished() == True). To queue trials for evaluation, please refer to enqueue_trial().

See also:

See *create_trial()* for how to create trials.

```
\label{parameters} \textbf{Parameters trial} \ (\texttt{optuna.trial.\_frozen.FrozenTrial}) - \textbf{Trial to add}.
```

Raises ValueError – If trial is an invalid state.

Return type None

```
add_trials(trials)
```

Add trials to study.

The trials are validated before being added.

```
import optuma

def objective(trial):
    x = trial.suggest_float("x", 0, 10)
    return x**2

study = optuma.create_study()
study.optimize(objective, n_trials=3)
assert len(study.trials) == 3

other_study = optuma.create_study()
other_study.add_trials(study.trials)
assert len(other_study.trials) == len(study.trials)

other_study.optimize(objective, n_trials=2)
assert len(other_study.trials) == len(study.trials) + 2
```

See also:

See add_trial() for addition of each trial.

```
Parameters trials (Iterable[optuna.trial._frozen.FrozenTrial]) - Trials to add.

Raises ValueError - If trials include invalid trial.

Return type None
```

ask(fixed_distributions=None)

Create a new trial from which hyperparameters can be suggested.

This method is part of an alternative to *optimize()* that allows controlling the lifetime of a trial outside the scope of func. Each call to this method should be followed by a call to *tell()* to finish the created trial.

See also:

The Ask-and-Tell Interface tutorial provides use-cases with examples.

Example

Getting the trial object with the ask() method.

```
import optuna

study = optuna.create_study()

trial = study.ask()

x = trial.suggest_float("x", -1, 1)

study.tell(trial, x**2)
```

Passing previously defined distributions to the ask() method.

```
import optuna

study = optuna.create_study()

distributions = {
    "optimizer": optuna.distributions.CategoricalDistribution(["adam", "sgd"]),
    "lr": optuna.distributions.FloatDistribution(0.0001, 0.1, log=True),
}

# You can pass the distributions previously defined.
trial = study.ask(fixed_distributions=distributions)

# `optimizer` and `lr` are already suggested and accessible with `trial.params`.
assert "optimizer" in trial.params
assert "lr" in trial.params
```

Parameters fixed_distributions (Optional[Dict[str, optuna.distributions. BaseDistribution]]) — A dictionary containing the parameter names and parameter's distributions. Each parameter in this dictionary is automatically suggested for the returned trial, even when the suggest method is not explicitly invoked by the user. If this argument is set to None, no parameter is automatically suggested.

Returns A Trial.

Return type optuna.trial._trial.Trial

```
property best_params: Dict[str, Any]
```

Return parameters of the best trial in the study.

Returns A dictionary containing parameters of the best trial.

Raises RuntimeError – If the study has more than one direction.

```
property best_trial: optuna.trial._frozen.FrozenTrial
```

Return the best trial in the study.

Returns A FrozenTrial object of the best trial.

Raises RuntimeError – If the study has more than one direction.

See also:

The Re-use the best trial tutorial provides a detailed example of how to use this method.

```
property best_trials: List[optuna.trial._frozen.FrozenTrial]
```

Return trials located at the Pareto front in the study.

A trial is located at the Pareto front if there are no trials that dominate the trial. It's called that a trial t0 dominates another trial t1 if $all(v0 \le v1)$ for v0, v1 in zip(t0.values, t1.values) and any(v0 < v1) for v0, v1 in zip(t0.values, t1.values) are held.

Returns A list of *FrozenTrial* objects.

```
property best_value: float
```

Return the best objective value in the study.

Returns A float representing the best objective value.

Raises RuntimeError – If the study has more than one direction.

```
property direction: optuna.study._study_direction.StudyDirection
```

Return the direction of the study.

```
Returns A StudyDirection object.
```

Raises RuntimeError – If the study has more than one direction.

```
property directions: List[optuna.study._study_direction.StudyDirection]
```

Return the directions of the study.

Returns A list of StudyDirection objects.

```
enqueue_trial(params, user_attrs=None)
```

Enqueue a trial with given parameter values.

You can fix the next sampling parameters which will be evaluated in your objective function.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", 0, 10)
    return x**2

study = optuna.create_study()
study.enqueue_trial({"x": 5})
study.enqueue_trial({"x": 0}, user_attrs={"memo": "optimal"})
study.optimize(objective, n_trials=2)

assert study.trials[0].params == {"x": 5}
assert study.trials[1].params == {"x": 0}
assert study.trials[1].user_attrs == {"memo": "optimal"}
```

Parameters

- params (Dict[str, Any]) Parameter values to pass your objective function.
- user_attrs (Optional[Dict[str, Any]]) A dictionary of user-specific attributes other than params.

Return type None

See also:

Please refer to Specify Hyperparameters Manually for the tutorial of specifying hyperparameters manually.

```
get_trials(deepcopy=True, states=None)
```

Return all trials in the study.

The returned trials are ordered by trial number.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -1, 1)
    return x**2

study = optuna.create_study()
study.optimize(objective, n_trials=3)

trials = study.get_trials()
assert len(trials) == 3
```

Parameters

- **deepcopy** (*bool*) Flag to control whether to apply copy. **deepcopy**() to the trials. Note that if you set the flag to False, you shouldn't mutate any fields of the returned trial. Otherwise the internal state of the study may corrupt and unexpected behavior may happen.
- **states** (Optional[Container[optuna.trial._state.TrialState]]) Trial states to filter on. If None, include all states.

Returns A list of *FrozenTrial* objects.

Return type *List*[optuna.trial._frozen.FrozenTrial]

Optimize an objective function.

Optimization is done by choosing a suitable set of hyperparameter values from a given range. Uses a sampler which implements the task of value suggestion based on a specified distribution. The sampler is specified in *create_study()* and the default choice for the sampler is TPE. See also *TPESampler* for more details on 'TPE'.

Optimization will be stopped when receiving a termination signal such as SIGINT and SIGTERM. Unlike other signals, a trial is automatically and cleanly failed when receiving SIGINT (Ctrl+C). If n_{jobs} is greater than one or if another signal than SIGINT is used, the interrupted trial state won't be properly updated.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -1, 1)
    return x**2

study = optuna.create_study()
study.optimize(objective, n_trials=3)
```

Parameters

- func (Callable[[optuna.trial._trial], Union[float, Sequence[float]]]) A callable that implements objective function.
- n_trials (Optional[int]) The number of trials for each process. If this argument is
 set to None, there is no limitation on the number of trials. If timeout is also set to None,
 the study continues to create trials until it receives a termination signal such as Ctrl+C or
 SIGTERM.

See also:

optuna.study.MaxTrialsCallback can ensure how many times trials will be performed across all processes.

- **timeout** (*Union* [*None*, *float*]) Stop study after the given number of second(s). If this argument is set to None, the study is executed without time limitation. If n_trials is also set to None, the study continues to create trials until it receives a termination signal such as Ctrl+C or SIGTERM.
- **n_jobs** (*int*) The number of parallel jobs. If this argument is set to –1, the number is set to CPU count.

Note: n_jobs allows parallelization using threading and may suffer from Python's GIL. It is recommended to use *process-based parallelization* if func is CPU bound.

- **catch** (*Tuple[Type[Exception]*, ...]) A study continues to run even when a trial raises one of the exceptions specified in this argument. Default is an empty tuple, i.e. the study will stop for any exception except for *TrialPruned*.
- callbacks (Optional[List[Callable[[optuna.study.study.Study, optuna.trial._frozen.FrozenTrial], None]]])—List of callback functions that are invoked at the end of each trial. Each function must accept two parameters with the following types in this order: Study and FrozenTrial.

See also:

See the tutorial of *Callback for Study.optimize* for how to use and implement callback functions.

• gc_after_trial (bool) – Flag to determine whether to automatically run garbage collection after each trial. Set to True to run the garbage collection, False otherwise. When it runs, it runs a full collection by internally calling gc.collect(). If you see an increase in memory consumption over several trials, try setting this flag to True.

See also:

How do I avoid running out of memory (OOM) when optimizing studies?

• **show_progress_bar** (*bool*) – Flag to show progress bars or not. To disable progress bar, set this False. Currently, progress bar is experimental feature and disabled when n_trials is None`, timeout not is None, and n_jobs ≠ 1.

Raises RuntimeError – If nested invocation of this method occurs.

Return type None

```
set_system_attr(key, value)
```

Set a system attribute to the study.

Note that Optuna internally uses this method to save system messages. Please use set_user_attr() to set users' attributes.

Parameters

- **key** (*str*) A key string of the attribute.
- value (Any) A value of the attribute. The value should be JSON serializable.

Return type None

```
set_user_attr(key, value)
```

Set a user attribute to the study.

See also:

See *user_attrs* for related attribute.

See also:

See the recipe on *User Attributes*.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", 0, 1)
    y = trial.suggest_float("y", 0, 1)
    return x**2 + y**2

study = optuna.create_study()

study.set_user_attr("objective function", "quadratic function")
study.set_user_attr("dimensions", 2)
study.set_user_attr("contributors", ["Akiba", "Sano"])

assert study.user_attrs == {
    "objective function": "quadratic function",
    "dimensions": 2,
    "contributors": ["Akiba", "Sano"],
}
```

Parameters

- **key** (*str*) A key string of the attribute.
- value (Any) A value of the attribute. The value should be JSON serializable.

Return type None

stop()

Exit from the current optimization loop after the running trials finish.

This method lets the running <code>optimize()</code> method return immediately after all trials which the <code>optimize()</code> method spawned finishes. This method does not affect any behaviors of parallel or successive study processes.

Example

```
import optuna

def objective(trial):
    if trial.number == 4:
        trial.study.stop()
    x = trial.suggest_float("x", 0, 10)
    return x**2

study = optuna.create_study()
study.optimize(objective, n_trials=10)
assert len(study.trials) == 5
```

Raises RuntimeError – If this method is called outside an objective function or callback.

Return type None

```
property system_attrs: Dict[str, Any]
```

Return system attributes.

Returns A dictionary containing all system attributes.

tell(trial, values=None, state=None, skip_if_finished=False)

Finish a trial created with ask().

See also:

The Ask-and-Tell Interface tutorial provides use-cases with examples.

Example

```
import optuna
from optuna.trial import TrialState
def f(x):
   return (x - 2) ** 2
def df(x):
   return 2 * x - 4
study = optuna.create_study()
n_{trials} = 30
for _ in range(n_trials):
   trial = study.ask()
   lr = trial.suggest_float("lr", 1e-5, 1e-1, log=True)
   # Iterative gradient descent objective function.
   x = 3 # Initial value.
   for step in range(128):
       y = f(x)
        trial.report(y, step=step)
        if trial.should_prune():
            # Finish the trial with the pruned state.
            study.tell(trial, state=TrialState.PRUNED)
            break
        gy = df(x)
       x -= gy * 1r
   else:
        # Finish the trial with the final value after all iterations.
        study.tell(trial, y)
```

Parameters

- trial (Union [optuna.trial._trial.Trial, int]) A Trial object or a trial number.
- values (Optional [Union [float, Sequence [float]]]) Optional objective value or a sequence of such values in case the study is used for multi-objective optimization. Argument must be provided if state is COMPLETE and should be None if state is FAIL or PRUNED.
- **state** (Optional[optuna.trial._state.TrialState]) State to be reported. Must be None, COMPLETE, FAIL or PRUNED. If state is None, it will be updated to COMPLETE or FAIL depending on whether validation for values reported succeed or not.

• **skip_if_finished** (*boo1*) – Flag to control whether exception should be raised when values for already finished trial are told. If True, tell is skipped without any error when the trial is already finished.

Raises

- TypeError If trial is not a Trial or an int.
- ValueError If any of the following. state is *COMPLETE* but values is None. state is *FAIL* or *PRUNED* but values is not None. state is not *COMPLETE*, *FAIL* or *PRUNED*. trial is a trial number but no trial exists with that number.

Returns A *FrozenTrial* representing the resulting trial. A returned trial is deep copied thus user can modify it as needed.

Return type optuna.trial._frozen.FrozenTrial

```
property trials: List[optuna.trial._frozen.FrozenTrial]
```

Return all trials in the study.

The returned trials are ordered by trial number.

This is a short form of self.get_trials(deepcopy=True, states=None).

Returns A list of *FrozenTrial* objects.

```
trials_dataframe(attrs=('number', 'value', 'datetime_start', 'datetime_complete', 'duration', 'params', 'user_attrs', 'system_attrs', 'state'), multi_index=False)
```

Export trials as a pandas DataFrame.

The DataFrame provides various features to analyze studies. It is also useful to draw a histogram of objective values and to export trials as a CSV file. If there are no trials, an empty DataFrame is returned.

Example

```
import optuna
import pandas

def objective(trial):
    x = trial.suggest_float("x", -1, 1)
    return x**2

study = optuna.create_study()
study.optimize(objective, n_trials=3)

# Create a dataframe from the study.
df = study.trials_dataframe()
assert isinstance(df, pandas.DataFrame)
assert df.shape[0] == 3 # n_trials.
```

Parameters

• attrs (Tuple[str, ...]) - Specifies field names of FrozenTrial to include them to a DataFrame of trials.

• multi_index (bool) - Specifies whether the returned DataFrame employs MultiIndex or not. Columns that are hierarchical by nature such as (params, x) will be flattened to params_x when set to False.

Returns A pandas DataFrame of trials in the *Study*.

Return type pd.DataFrame

Note: If value is in attrs during multi-objective optimization, it is implicitly replaced with values.

```
property user_attrs: Dict[str, Any]
```

Return user attributes.

See also:

See set_user_attr() for related method.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", 0, 1)
    y = trial.suggest_float("y", 0, 1)
    return x**2 + y**2

study = optuna.create_study()

study.set_user_attr("objective function", "quadratic function")
study.set_user_attr("dimensions", 2)
study.set_user_attr("contributors", ["Akiba", "Sano"])

assert study.user_attrs == {
    "objective function": "quadratic function",
    "dimensions": 2,
    "contributors": ["Akiba", "Sano"],
}
```

Returns A dictionary containing all user attributes.

optuna.study.create study

```
optuna.study.create_study(*, storage=None, sampler=None, pruner=None, study_name=None, direction=None, load_if_exists=False, directions=None)
```

Create a new Study.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", 0, 10)
    return x**2

study = optuna.create_study()
study.optimize(objective, n_trials=3)
```

Parameters

• **storage** (Optional [Union [str, optuna.storages._base.BaseStorage]]) — Database URL. If this argument is set to None, in-memory storage is used, and the Study will not be persistent.

Note:

When a database URL is passed, Optuna internally uses SQLAlchemy to handle the database. Please refer to SQLAlchemy's document for further details. If you want to specify non-default options to SQLAlchemy Engine, you can instantiate *RDBStorage* with your desired options and pass it to the storage argument instead of a URL.

- sampler (Optional [optuna.samplers._base.BaseSampler]) A sampler object that implements background algorithm for value suggestion. If None is specified, TPESampler is used during single-objective optimization and NSGAIISampler during multi-objective optimization. See also samplers.
- **pruner** (Optional [optuna.pruners._base.BasePruner]) A pruner object that decides early stopping of unpromising trials. If None is specified, MedianPruner is used as the default. See also pruners.
- **study_name** (*Optional[str]*) Study's name. If this argument is set to None, a unique name is generated automatically.
- direction (Optional[Union[str, optuna.study._study_direction. StudyDirection]]) Direction of optimization. Set minimize for minimization and maximize for maximization. You can also pass the corresponding StudyDirection object.

Note: If none of *direction* and *directions* are specified, the direction of the study is set to "minimize".

- load_if_exists (bool) Flag to control the behavior to handle a conflict of study names. In the case where a study named study_name already exists in the storage, a DuplicatedStudyError is raised if load_if_exists is set to False. Otherwise, the creation of the study is skipped, and the existing one is returned.
- directions (Optional[Sequence[Union[str, optuna.study._study_direction.StudyDirection]]]) A sequence of directions during multi-objective optimization.

Returns A *Study* object.

Raises ValueError – If the length of directions is zero. Or, if direction is neither 'minimize' nor 'maximize' when it is a string. Or, if the element of directions is neither *minimize* nor *maximize*. Or, if both direction and directions are specified.

Return type optuna.study.study.Study

See also:

```
optuna.create_study() is an alias of optuna.study.create_study().
```

See also:

The Saving/Resuming Study with RDB Backend tutorial provides concrete examples to save and resume optimization using RDB.

optuna.study.load_study

```
optuna.study.load_study(*, study_name, storage, sampler=None, pruner=None)

Load the existing Study that has the specified name.
```

Example

Parameters

- **study_name** (*Optional[str]*) Study's name. Each study has a unique name as an identifier. If None, checks whether the storage contains a single study, and if so loads that study.
- **storage** (*Union[str, optuna.storages._base.BaseStorage]*) Database URL such as sqlite:///example.db. Please see also the documentation of *create_study()* for further details.
- **sampler** (Optional [optuna.samplers._base.BaseSampler]) A sampler object that implements background algorithm for value suggestion. If None is specified, TPESampler is used as the default. See also samplers.
- **pruner** (Optional[optuna.pruners._base.BasePruner]) A pruner object that decides early stopping of unpromising trials. If None is specified, MedianPruner is used as the default. See also pruners.

Raises ValueError – If study_name is None and the storage contains more than 1 study.

```
Return type optuna.study.study.Study
```

See also:

```
optuna.load_study() is an alias of optuna.study.load_study().
```

optuna.study.delete study

```
optuna.study.delete_study(*, study_name, storage)

Delete a Study object.
```

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

study = optuna.create_study(study_name="example-study", storage="sqlite://example.
    db")
    study.optimize(objective, n_trials=3)

optuna.delete_study(study_name="example-study", storage="sqlite://example.db")
```

Parameters

- **study_name** (*str*) Study's name.
- **storage** (*Union[str, optuna.storages._base.BaseStorage]*) Database URL such as sqlite:///example.db. Please see also the documentation of *create_study()* for further details.

Return type None

See also:

```
optuna.delete_study() is an alias of optuna.study.delete_study().
```

optuna.study.copy_study

```
optuna.study.copy_study(*, from_study_name, from_storage, to_storage, to_study_name=None)
Copy study from one storage to another.
```

The direction(s) of the objective(s) in the study, trials, user attributes and system attributes are copied.

Note: *copy_study()* copies a study even if the optimization is working on. It means users will get a copied study that contains a trial that is not finished.

Example

```
import optuna
def objective(trial):
    x = trial.suggest_float("x", -10, 10)
   return (x - 2) ** 2
study = optuna.create_study(
    study_name="example-study",
    storage="sqlite:///example.db",
study.optimize(objective, n_trials=3)
optuna.copy_study(
    from_study_name="example-study",
    from_storage="sqlite:///example.db",
    to_storage="sqlite:///example_copy.db",
)
study = optuna.load_study(
    study_name=None,
    storage="sqlite:///example_copy.db",
)
```

Parameters

- **from_study_name** (*str*) Name of study.
- from_storage (Union[str, optuna.storages._base.BaseStorage]) Source database URL such as sqlite:///example.db. Please see also the documentation of create_study() for further details.
- to_storage (Union[str, optuma.storages._base.BaseStorage]) Destination database URL.
- to_study_name (Optional[str]) Name of the created study. If omitted, from_study_name is used.

Raises *DuplicatedStudyError* – If a study with a conflicting name already exists in the destination storage.

Return type None

optuna.study.get_all_study_summaries

```
optuna.study.get_all_study_summaries(storage, include_best_trial=True)
```

Get all history of studies stored in a specified storage.

Example

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -10, 10)
    return (x - 2) ** 2

study = optuna.create_study(study_name="example-study", storage="sqlite:///example.
    db")
study.optimize(objective, n_trials=3)

study_summaries = optuna.study.get_all_study_summaries(storage="sqlite:///example.db
    ")
assert len(study_summaries) == 1

study_summary = study_summaries[0]
assert study_summary.study_name == "example-study"
```

Parameters

- **storage** (*Union[str, optuna.storages._base.BaseStorage]*) Database URL such as sqlite:///example.db. Please see also the documentation of *create_study()* for further details.
- **include_best_trial** (*bool*) Include the best trials if exist. It potentially increases the number of queries and may take longer to fetch summaries depending on the storage.

Returns List of study history summarized as *StudySummary* objects.

Return type *List[optuna.study._study_summary.StudySummary]*

See also:

```
optuna.get_all_study_summaries() is an alias of optuna.study.get_all_study_summaries().
```

optuna.study.MaxTrialsCallback

```
\textbf{class} \ optuna.study. \textbf{MaxTrialsCallback} (\textit{n\_trials}, \textit{states} = (\textit{TrialState}. COMPLETE,))
```

Set a maximum number of trials before ending the study.

While the n_trials argument of optuma.optimize sets the number of trials that will be run, you may want to continue running until you have a certain number of successfully completed trials or stop the study when you have a certain number of trials that fail. This <code>MaxTrialsCallback</code> class allows you to set a maximum number of trials for a particular <code>TrialState</code> before stopping the study.

Example

```
import optuna
from optuna.study import MaxTrialsCallback
from optuna.trial import TrialState

def objective(trial):
    x = trial.suggest_float("x", -1, 1)
    return x**2

study = optuna.create_study()
study.optimize(
    objective,
    callbacks=[MaxTrialsCallback(10, states=(TrialState.COMPLETE,))],
)
```

Parameters

- **n_trials** (*int*) The max number of trials. Must be set to an integer.
- states (Optional [Container [optuna.trial._state.TrialState]]) Tuple of the TrialState to be counted towards the max trials limit. Default value is (TrialState. COMPLETE,). If None, count all states.

Return type None

optuna.study.StudyDirection

class optuna.study.StudyDirection(value)

Direction of a Study.

NOT_SET

Direction has not been set.

MINIMIZE

Study minimizes the objective function.

MAXIMIZE

Study maximizes the objective function.

Attributes

NOT_SET

MINIMIZE

MAXIMIZE

optuna.study.StudySummary

class optuna.study.**StudySummary**(*study_name*, *direction*, *best_trial*, *user_attrs*, *system_attrs*, *n_trials*, *datetime_start*, *study_id*, *, *directions=None*)

Basic attributes and aggregated results of a Study.

See also optuna.study.get_all_study_summaries().

Parameters

- study_name (str) -
- direction (Optional [optuna.study._study_direction.StudyDirection]) -
- best_trial (Optional[optuna.trial._frozen.FrozenTrial]) -
- user_attrs(Dict[str, Any]) -
- system_attrs (Dict[str, Any]) -
- n_trials(int)-
- datetime_start(Optional[datetime.datetime]) -
- study_id(int)-
- **directions** (Optional[Sequence[optuna.study._study_direction. StudyDirection]]) -

study_name

Name of the Study.

direction

StudyDirection of the Study.

Note: This attribute is only available during single-objective optimization.

directions

A sequence of StudyDirection objects.

best_trial

optuna.trial.FrozenTrial with best objective value in the Study.

user_attrs

Dictionary that contains the attributes of the *Study* set with *optuna.study.Study.set_user_attr()*.

system_attrs

Dictionary that contains the attributes of the *Study* internally set by Optuna.

n_trials

The number of trials ran in the *Study*.

datetime_start

Datetime where the *Study* started.

Attributes

direction			
directions			

6.3.13 optuna.trial

The trial module contains Trial related classes and functions.

A *Trial* instance represents a process of evaluating an objective function. This instance is passed to an objective function and provides interfaces to get parameter suggestion, manage the trial's state, and set/get user-defined attributes of the trial, so that Optuna users can define a custom objective function through the interfaces. Basically, Optuna users only use it in their custom objective functions.

optuna.trial.Trial	A trial is a process of evaluating an objective function.
optuna.trial.FixedTrial	A trial class which suggests a fixed value for each pa-
	rameter.
optuna.trial.FrozenTrial	Status and results of a <i>Trial</i> .
optuna.trial.TrialState	State of a Trial.
optuna.trial.create_trial	Create a new FrozenTrial.

optuna.trial.Trial

class optuna.trial.Trial(study, trial_id)

A trial is a process of evaluating an objective function.

This object is passed to an objective function and provides interfaces to get parameter suggestion, manage the trial's state, and set/get user-defined attributes of the trial.

Note that the direct use of this constructor is not recommended. This object is seamlessly instantiated and passed to the objective function behind the <code>optuna.study.Study.optimize()</code> method; hence library users do not care about instantiation of this object.

Parameters

- study (optuna.study.Study) A Study object.
- **trial_id** (*int*) A trial ID that is automatically generated.

Return type None

Methods

report(value, step)	Report an objective function value for a given step.
<pre>set_system_attr(key, value)</pre>	Set system attributes to the trial.
set_user_attr(key, value)	Set user attributes to the trial.
should_prune()	Suggest whether the trial should be pruned or not.
<pre>suggest_categorical(name, choices)</pre>	Suggest a value for the categorical parameter.
<pre>suggest_discrete_uniform(name, low, high, q)</pre>	Suggest a value for the discrete parameter.
<pre>suggest_float(name, low, high, *[, step, log])</pre>	Suggest a value for the floating point parameter.
<pre>suggest_int(name, low, high[, step, log])</pre>	Suggest a value for the integer parameter.
suggest_loguniform(name, low, high)	Suggest a value for the continuous parameter.
suggest_uniform(name, low, high)	Suggest a value for the continuous parameter.

Attributes

datetime_start	Return start datetime.
distributions	Return distributions of parameters to be optimized.
number	Return trial's number which is consecutive and
	unique in a study.
params	Return parameters to be optimized.
system_attrs	Return system attributes.
user_attrs	Return user attributes.

property datetime_start: Optional[datetime.datetime]

Return start datetime.

Returns Datetime where the *Trial* started.

property distributions: Dict[str, optuna.distributions.BaseDistribution]

Return distributions of parameters to be optimized.

Returns A dictionary containing all distributions.

property number: int

Return trial's number which is consecutive and unique in a study.

Returns A trial number.

property params: Dict[str, Any]

Return parameters to be optimized.

Returns A dictionary containing all parameters.

report(value, step)

Report an objective function value for a given step.

The reported values are used by the pruners to determine whether this trial should be pruned.

See also:

Please refer to BasePruner.

Note: The reported value is converted to float type by applying float() function internally. Thus, it accepts all float-like types (e.g., numpy.float32). If the conversion fails, a TypeError is raised.

Note: If this method is called multiple times at the same step in a trial, the reported value only the first time is stored and the reported values from the second time are ignored.

Example

Report intermediate scores of SGDClassifier training.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.linear_model import SGDClassifier
from sklearn.model_selection import train_test_split
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)
def objective(trial):
   clf = SGDClassifier(random_state=0)
   for step in range(100):
        clf.partial_fit(X_train, y_train, np.unique(y))
        intermediate_value = clf.score(X_valid, y_valid)
        trial.report(intermediate_value, step=step)
        if trial.should_prune():
            raise optuna.TrialPruned()
   return clf.score(X_valid, y_valid)
study = optuna.create_study(direction="maximize")
study.optimize(objective, n_trials=3)
```

Parameters

- **value** (*float*) A value returned from the objective function.
- **step** (*int*) Step of the trial (e.g., Epoch of neural network training). Note that pruners assume that step starts at zero. For example, *MedianPruner* simply checks if step is less than n_warmup_steps as the warmup mechanism.

Raises

- NotImplementedError If trial is being used for multi-objective optimization.
- ValueError If step is negative.
- **TypeError** If the type of value is not float.

Return type None

```
set_system_attr(key, value)
```

Set system attributes to the trial.

Note that Optuna internally uses this method to save system messages such as failure reason of trials. Please use <code>set_user_attr()</code> to set users' attributes.

Parameters

- **key** (*str*) A key string of the attribute.
- value (Any) A value of the attribute. The value should be JSON serializable.

Return type None

```
set_user_attr(key, value)
```

Set user attributes to the trial.

The user attributes in the trial can be access via optuna.trial.Trial.user_attrs().

See also:

See the recipe on *User Attributes*.

Example

Save fixed hyperparameters of neural network training.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.model_selection import train_test_split
from sklearn.neural_network import MLPClassifier
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y, random_state=0)
def objective(trial):
   trial.set_user_attr("BATCHSIZE", 128)
   momentum = trial.suggest_float("momentum", 0, 1.0)
   clf = MLPClassifier(
       hidden_layer_sizes=(100, 50),
        batch_size=trial.user_attrs["BATCHSIZE"],
       momentum=momentum,
        solver="sqd",
        random_state=0,
   clf.fit(X_train, y_train)
   return clf.score(X_valid, y_valid)
study = optuna.create_study(direction="maximize")
study optimize(objective, n_trials=3)
assert "BATCHSIZE" in study.best_trial.user_attrs.keys()
assert study.best_trial.user_attrs["BATCHSIZE"] == 128
```

Parameters

- **key** (*str*) A key string of the attribute.
- value (Any) A value of the attribute. The value should be JSON serializable.

Return type None

should_prune()

Suggest whether the trial should be pruned or not.

The suggestion is made by a pruning algorithm associated with the trial and is based on previously reported values. The algorithm can be specified when constructing a *Study*.

Note: If no values have been reported, the algorithm cannot make meaningful suggestions. Similarly, if this method is called multiple times with the exact same set of reported values, the suggestions will be the same.

See also:

Please refer to the example code in optuna.trial.Trial.report().

Returns A boolean value. If True, the trial should be pruned according to the configured pruning algorithm. Otherwise, the trial should continue.

Raises NotImplementedError – If trial is being used for multi-objective optimization.

Return type bool

suggest_categorical(name, choices)

Suggest a value for the categorical parameter.

The value is sampled from choices.

Example

Suggest a kernel function of SVC.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.model_selection import train_test_split
from sklearn.svm import SVC

import optuna

X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)

def objective(trial):
    kernel = trial.suggest_categorical("kernel", ["linear", "poly", "rbf"])
    clf = SVC(kernel=kernel, gamma="scale", random_state=0)
    clf.fit(X_train, y_train)
    return clf.score(X_valid, y_valid)
```

(continues on next page)

(continued from previous page)

```
study = optuna.create_study(direction="maximize")
study.optimize(objective, n_trials=3)
```

Parameters

- name (str) A parameter name.
- choices (Sequence [Union [None, bool, int, float, str]]) Parameter value candidates.

Return type *Union*[None, bool, int, float, str]

See also:

CategoricalDistribution.

Returns A suggested value.

Parameters

- name (str) -
- choices (Sequence [Union [None, bool, int, float, str]]) -

Return type *Union*[None, bool, int, float, str]

See also:

2. Pythonic Search Space tutorial describes more details and flexible usages.

```
suggest_discrete_uniform(name, low, high, q)
```

Suggest a value for the discrete parameter.

The value is sampled from the range [low, high], and the step of discretization is q. More specifically, this method returns one of the values in the sequence low, low +q, low $+2q,\ldots$, low $+kq \leq \text{high}$, where k denotes an integer. Note that high may be changed due to round-off errors if q is not an integer. Please check warning messages to find the changed values.

Parameters

- **name** (*str*) A parameter name.
- **low** (*float*) Lower endpoint of the range of suggested values. low is included in the range.
- **high** (*float*) Upper endpoint of the range of suggested values. **high** is included in the range.
- **q** (*float*) A step of discretization.

Returns A suggested float value.

Return type float

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

```
suggest_float(name, low, high, *, step=None, log=False)
```

Suggest a value for the floating point parameter.

New in version 1.3.0.

Example

Suggest a momentum, learning rate and scaling factor of learning rate for neural network training.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.model_selection import train_test_split
from sklearn.neural_network import MLPClassifier
import optuna
X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y, random_state=0)
def objective(trial):
   momentum = trial.suggest_float("momentum", 0.0, 1.0)
   learning_rate_init = trial.suggest_float(
        "learning_rate_init", 1e-5, 1e-3, log=True
   )
   power_t = trial.suggest_float("power_t", 0.2, 0.8, step=0.1)
   clf = MLPClassifier(
       hidden_layer_sizes=(100, 50),
       momentum=momentum,
        learning_rate_init=learning_rate_init,
        solver="sgd",
        random_state=0,
        power_t=power_t,
   clf.fit(X_train, y_train)
   return clf.score(X_valid, y_valid)
study = optuna.create_study(direction="maximize")
study.optimize(objective, n_trials=3)
```

Parameters

- **name** (*str*) A parameter name.
- **low** (*float*) Lower endpoint of the range of suggested values. **low** is included in the range.
- **high** (*float*) Upper endpoint of the range of suggested values. **high** is included in the range.
- **step** (*Union* [*None*, *float*]) A step of discretization.

Note: The step and log arguments cannot be used at the same time. To set the step argument to a float number, set the log argument to False.

• log (bool) – A flag to sample the value from the log domain or not. If log is true, the value is sampled from the range in the log domain. Otherwise, the value is sampled from the range in the linear domain.

Note: The step and log arguments cannot be used at the same time. To set the log argument to True, set the step argument to None.

Raises ValueError - If step is not None and log = True are specified.

Returns A suggested float value.

Return type float

See also:

2. Pythonic Search Space tutorial describes more details and flexible usages.

```
suggest_int(name, low, high, step=1, log=False)
```

Suggest a value for the integer parameter.

The value is sampled from the integers in [low, high].

Example

Suggest the number of trees in RandomForestClassifier.

```
import numpy as np
from sklearn.datasets import load_iris
from sklearn.ensemble import RandomForestClassifier
from sklearn.model_selection import train_test_split

import optuna

X, y = load_iris(return_X_y=True)
X_train, X_valid, y_train, y_valid = train_test_split(X, y)

def objective(trial):
    n_estimators = trial.suggest_int("n_estimators", 50, 400)
    clf = RandomForestClassifier(n_estimators=n_estimators, random_state=0)
    clf.fit(X_train, y_train)
    return clf.score(X_valid, y_valid)

study = optuna.create_study(direction="maximize")
study.optimize(objective, n_trials=3)
```

Parameters

• name (str) – A parameter name.

- low (int) Lower endpoint of the range of suggested values. low is included in the range.
- **high** (*int*) Upper endpoint of the range of suggested values. **high** is included in the range.
- **step** (*int*) A step of discretization.

Note: Note that high is modified if the range is not divisible by step. Please check the warning messages to find the changed values.

Note: The method returns one of the values in the sequence low, low + step, low + 2 * step, ..., low + k * step \leq high, where k denotes an integer.

Note: The step != 1 and log arguments cannot be used at the same time. To set the step argument step ≥ 2 , set the log argument to False.

• **log** (*bool*) – A flag to sample the value from the log domain or not.

Note: If log is true, at first, the range of suggested values is divided into grid points of width 1. The range of suggested values is then converted to a log domain, from which a value is sampled. The uniformly sampled value is re-converted to the original domain and rounded to the nearest grid point that we just split, and the suggested value is determined. For example, if low = 2 and high = 8, then the range of suggested values is [2, 3, 4, 5, 6, 7, 8] and lower values tend to be more sampled than higher values.

Note: The step != 1 and log arguments cannot be used at the same time. To set the log argument to log argumen

Return type int

See also:

2. Pythonic Search Space tutorial describes more details and flexible usages.

suggest_loguniform(name, low, high)

Suggest a value for the continuous parameter.

The value is sampled from the range [low, high) in the log domain. When low = high, the value of low will be returned.

Parameters

- name (str) A parameter name.
- **low** (*float*) Lower endpoint of the range of suggested values. **low** is included in the range.
- **high** (*float*) Upper endpoint of the range of suggested values. **high** is included in the range.

Returns A suggested float value.

Return type float

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

suggest_uniform(name, low, high)

Suggest a value for the continuous parameter.

The value is sampled from the range [low, high] in the linear domain. When low = high, the value of low will be returned.

Parameters

- name (str) A parameter name.
- **low** (*float*) Lower endpoint of the range of suggested values. low is included in the range.
- **high** (*float*) Upper endpoint of the range of suggested values. high is included in the range.

Returns A suggested float value.

Return type float

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

```
property system_attrs: Dict[str, Any]
```

Return system attributes.

Returns A dictionary containing all system attributes.

```
property user_attrs: Dict[str, Any]
```

Return user attributes.

Returns A dictionary containing all user attributes.

optuna.trial.FixedTrial

```
class optuna.trial.FixedTrial(params, number=0)
```

A trial class which suggests a fixed value for each parameter.

This object has the same methods as *Trial*, and it suggests pre-defined parameter values. The parameter values can be determined at the construction of the *FixedTrial* object. In contrast to *Trial*, *FixedTrial* does not depend on *Study*, and it is useful for deploying optimization results.

Example

Evaluate an objective function with parameter values given by a user.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x**2 + y

assert objective(optuna.trial.FixedTrial({"x": 1, "y": 0})) == 1
```

Note: Please refer to *Trial* for details of methods and properties.

Parameters

- params (Dict[str, Any]) A dictionary containing all parameters.
- number (int) A trial number. Defaults to 0.

Return type None

Methods

```
report(value, step)

set_system_attr(key, value)

set_user_attr(key, value)

should_prune()

suggest_categorical(name, choices)

suggest_discrete_uniform(name, low, high, q)

suggest_float(name, low, high, *[, step, log])

suggest_int(name, low, high[, step, log])

suggest_loguniform(name, low, high)

suggest_uniform(name, low, high)
```

Attributes

datetime_start
distributions
number
params
system_attrs
user_attrs

suggest_discrete_uniform(name, low, high, q)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

- name (str) -
- low (float) -
- high (float) -
- q(float)-

Return type float

suggest_loguniform(name, low, high)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

- name (str) -
- low (float) -
- high (float) -

Return type float

suggest_uniform(name, low, high)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

- name (str) -
- low (float) -
- high (float) -

Return type float

optuna.trial.FrozenTrial

Status and results of a Trial.

This object has the same methods as *Trial*, and it suggests best parameter values among performed trials. In contrast to *Trial*, *FrozenTrial* does not depend on *Study*, and it is useful for deploying optimization results.

Example

Re-evaluate an objective function with parameter values optimized study.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -1, 1)
    return x**2

study = optuna.create_study()
study.optimize(objective, n_trials=3)

assert objective(study.best_trial) == study.best_value
```

Note: Instances are mutable, despite the name. For instance, set_user_attr() will update user attributes of objects in-place.

Example:

Overwritten attributes.

```
import copy
import datetime
import optuna
def objective(trial):
   x = trial.suggest_float("x", -1, 1)
   # this user attribute always differs
   trial.set_user_attr("evaluation time", datetime.datetime.now())
   return x**2
study = optuna.create_study()
study.optimize(objective, n_trials=3)
best_trial = study.best_trial
best_trial_copy = copy.deepcopy(best_trial)
# re-evaluate
objective(best_trial)
# the user attribute is overwritten by re-evaluation
assert best_trial.user_attrs != best_trial_copy.user_attrs
```

Note: Please refer to *Trial* for details of methods and properties.

number

Unique and consecutive number of *Trial* for each *Study*. Note that this field uses zero-based numbering.

state

TrialState of the Trial.

value

Objective value of the *Trial*.

values

Sequence of objective values of the *Trial*. The length is greater than 1 if the problem is multi-objective optimization.

datetime_start

Datetime where the Trial started.

datetime_complete

Datetime where the Trial finished.

params

Dictionary that contains suggested parameters.

user_attrs

Dictionary that contains the attributes of the Trial set with optuna.trial.Trial.set_user_attr().

intermediate_values

Intermediate objective values set with optuna.trial.Trial.report().

Raises ValueError – If both value and values are specified.

Parameters

- number (int) -
- state (optuna.trial._state.TrialState) -
- value (Optional[float]) -
- datetime_start(Optional[datetime.datetime]) -
- datetime_complete(Optional[datetime.datetime]) -
- params (Dict[str, Any]) -
- distributions (Dict[str, optuna.distributions.BaseDistribution]) -
- user_attrs (Dict[str, Any]) -
- system_attrs (Dict[str, Any]) -
- intermediate_values (Dict[int, float]) -
- trial_id(int)-
- values (Optional [Sequence[float]]) -

Return type None

Methods

report(value, step)	Interface of report function.
set_system_attr(key, value)	
4	
set_user_attr(key, value)	
should_prune()	Suggest whether the trial should be pruned or not.
<pre>suggest_categorical(name, choices)</pre>	
suggest_discrete_uniform(name, low, high, q)	
<pre>suggest_float(name, low, high, *[, step, log])</pre>	
<pre>suggest_int(name, low, high[, step, log])</pre>	
avagagt laguni farm(nama lay high)	
suggest_loguniform(name, low, high)	
suggest_uniform(name, low, high)	

Attributes

datetime_start	
distributions	Dictionary that contains the distributions of params.
duration	Return the elapsed time taken to complete the trial.
last_step	Return the maximum step of <i>intermediate_values</i> in the trial.
number	
params	
system_attrs	
user_attrs	
value	
values	

property distributions: Dict[str, optuna.distributions.BaseDistribution]

Dictionary that contains the distributions of params.

property duration: Optional[datetime.timedelta]

Return the elapsed time taken to complete the trial.

Returns The duration.

property last_step: Optional[int]

Return the maximum step of *intermediate_values* in the trial.

Returns The maximum step of intermediates.

report(value, step)

Interface of report function.

Since FrozenTrial is not pruned, this report function does nothing.

See also:

Please refer to should_prune().

Parameters

- **value** (*float*) A value returned from the objective function.
- **step** (*int*) Step of the trial (e.g., Epoch of neural network training). Note that pruners assume that step starts at zero. For example, *MedianPruner* simply checks if step is less than n_warmup_steps as the warmup mechanism.

Return type None

should_prune()

Suggest whether the trial should be pruned or not.

The suggestion is always False regardless of a pruning algorithm.

Note: FrozenTrial only samples one combination of parameters.

Returns False.

Return type bool

suggest_discrete_uniform(name, low, high, q)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

- name (str) -
- low (float) -
- high (float) -
- q (float) -

Return type float

suggest_loguniform(name, low, high)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

- name (str) -
- low (float) -
- high (float) -

Return type float

suggest_uniform(name, low, high)

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v6.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Use suggest_float() instead.

Parameters

```
• low (float) -
                  • high (float) -
              Return type float
optuna.trial.TrialState
class optuna.trial.TrialState(value)
     State of a Trial.
     RUNNING
          The Trial is running.
     WAITING
          The Trial is waiting and unfinished.
     COMPLETE
          The Trial has been finished without any error.
     PRUNED
          The Trial has been pruned with TrialPruned.
     FAIL
          The Trial has failed due to an uncaught error.
     Methods
      is_finished()
     Attributes
      RUNNING
       COMPLETE
      PRUNED
      FAIL
       WAITING
```

• name (str) -

optuna.trial.create trial

```
optuna.trial.create_trial(*, state=TrialState.COMPLETE, value=None, values=None, params=None, distributions=None, user_attrs=None, system_attrs=None, intermediate_values=None)
```

Create a new FrozenTrial.

Example

```
import optuna
from optuna.distributions import CategoricalDistribution
from optuna.distributions import FloatDistribution

trial = optuna.trial.create_trial(
    params={"x": 1.0, "y": 0},
    distributions={
        "x": FloatDistribution(0, 10),
        "y": CategoricalDistribution([-1, 0, 1]),
    },
    value=5.0,
)

assert isinstance(trial, optuna.trial.FrozenTrial)
assert trial.value == 5.0
assert trial.params == {"x": 1.0, "y": 0}
```

See also:

See add_trial() for how this function can be used to create a study from existing trials.

Note: Please note that this is a low-level API. In general, trials that are passed to objective functions are created inside <code>optimize()</code>.

Note: When state is *TrialState.COMPLETE*, the following parameters are required:

- params
- distributions
- value or values

Parameters

- state (optuna.trial._state.TrialState) Trial state.
- value (Union[None, float]) Trial objective value. Must be specified if state is TrialState.COMPLETE.
- **values** (Optional[Sequence[float]]) Sequence of the trial objective values. The length is greater than 1 if the problem is multi-objective optimization. Must be specified if state is TrialState.COMPLETE.
- params (Optional[Dict[str, Any]]) Dictionary with suggested parameters of the trial.

- distributions (Optional[Dict[str, optuna.distributions. BaseDistribution]]) Dictionary with parameter distributions of the trial.
- user_attrs (Optional [Dict[str, Any]]) Dictionary with user attributes.
- **system_attrs** (Optional[Dict[str, Any]]) Dictionary with system attributes. Should not have to be used for most users.
- intermediate_values (Optional[Dict[int, float]]) Dictionary with intermediate objective values of the trial.

Returns Created trial.

Raises ValueError – If both value and values are specified.

Return type optuna.trial._frozen.FrozenTrial

6.3.14 optuna.visualization

The *visualization* module provides utility functions for plotting the optimization process using plotly and matplotlib. Plotting functions generally take a *Study* object and optional parameters are passed as a list to the params argument.

Note: In the *optuna.visualization* module, the following functions use plotly to create figures, but JupyterLab cannot render them by default. Please follow this installation guide to show figures in JupyterLab.

Note: The *plot_param_importances()* requires the Python package of scikit-learn.

optuna.visualization.plot_contour	Plot the parameter relationship as contour plot in a study.	
optuna.visualization.plot_edf	Plot the objective value EDF (empirical distribution	
	function) of a study.	
optuna.visualization.	Plot intermediate values of all trials in a study.	
plot_intermediate_values		
optuna.visualization.	Plot optimization history of all trials in a study.	
plot_optimization_history		
optuna.visualization.	Plot the high-dimensional parameter relationships in a	
plot_parallel_coordinate	study.	
optuna.visualization.	Plot hyperparameter importances.	
plot_param_importances		
optuna.visualization.plot_pareto_front	Plot the Pareto front of a study.	
optuna.visualization.plot_slice	Plot the parameter relationship as slice plot in a study.	
optuna.visualization.is_available	Returns whether visualization with plotly is available or	
	not.	

optuna.visualization.plot contour

optuna.visualization.plot_contour(study, params=None, *, target=None, target_name='Objective Value')

Plot the parameter relationship as contour plot in a study.

Note that, if a parameter contains missing values, a trial with missing values is not plotted.

Example

The following code snippet shows how to plot the parameter relationship as contour plot.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x ** 2 + y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=30)

fig = optuna.visualization.plot_contour(study, params=["x", "y"])
fig.show()
```

Parameters

- **study** (optuna.study.study) A *Study* object whose trials are plotted for their target values.
- params (Optional [List[str]]) Parameter list to visualize. The default is all parameters.
- target (Optional [Callable [[optuna.trial._frozen.FrozenTrial], float]])

 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

• **target_name** (*str*) – Target's name to display on the color bar.

Returns A plotly.graph_objs.Figure object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type plotly.graph_objs._figure.Figure

optuna.visualization.plot edf

```
optuna.visualization.plot_edf(study, *, target=None, target_name='Objective Value')
```

Plot the objective value EDF (empirical distribution function) of a study.

Note that only the complete trials are considered when plotting the EDF.

Note: EDF is useful to analyze and improve search spaces. For instance, you can see a practical use case of EDF in the paper Designing Network Design Spaces.

Note: The plotted EDF assumes that the value of the objective function is in accordance with the uniform distribution over the objective space.

Example

The following code snippet shows how to plot EDF.

```
import math
import optuna
def ackley(x, y):
    a = 20 * math.exp(-0.2 * math.sqrt(0.5 * (x ** 2 + y ** 2)))
    b = math.exp(0.5 * (math.cos(2 * math.pi * x) + math.cos(2 * math.pi * y)))
    return -a - b + math.e + 20
def objective(trial, low, high):
   x = trial.suggest_float("x", low, high)
   y = trial.suggest_float("y", low, high)
   return ackley(x, y)
sampler = optuna.samplers.RandomSampler(seed=10)
# Widest search space.
study0 = optuna.create_study(study_name="x=[0,5), y=[0,5)", sampler=sampler)
study0.optimize(lambda t: objective(t, 0, 5), n_trials=500)
# Narrower search space.
study1 = optuna.create_study(study_name="x=[0,4), y=[0,4)", sampler=sampler)
study1.optimize(lambda t: objective(t, 0, 4), n_trials=500)
# Narrowest search space but it doesn't include the global optimum point.
study2 = optuna.create_study(study_name="x=[1,3), y=[1,3)", sampler=sampler)
study2.optimize(lambda t: objective(t, 1, 3), n_trials=500)
fig = optuna.visualization.plot_edf([study0, study1, study2])
fig.show()
```

Parameters

- **study** (*Union*[optuna.study.study.Study, *Sequence*[optuna.study.study.Study]]) A target *Study* object. You can pass multiple studies if you want to compare those EDFs.
- target (Optional[Callable[[optuna.trial._frozen.FrozenTrial], float]])

 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

• **target_name** (*str*) – Target's name to display on the axis label.

Returns A plotly.graph_objs.Figure object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type plotly.graph_objs._figure.Figure

optuna.visualization.plot_intermediate_values

```
optuna.visualization.plot_intermediate_values(study)
```

Plot intermediate values of all trials in a study.

Example

The following code snippet shows how to plot intermediate values.

```
import optuna

def f(x):
    return (x - 2) ** 2

def df(x):
    return 2 * x - 4

def objective(trial):
    lr = trial.suggest_float("lr", 1e-5, 1e-1, log=True)

    x = 3
    for step in range(128):
        y = f(x)

        trial.report(y, step=step)
        if trial.should_prune():
            raise optuna.TrialPruned()

        gy = df(x)
        x -= gy * lr
```

(continues on next page)

```
return y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=16)

fig = optuna.visualization.plot_intermediate_values(study)
fig.show()
```

Parameters study (optuna.study.study.Study) – A *Study* object whose trials are plotted for their intermediate values.

Returns A plotly.graph_objs.Figure object.

Return type plotly.graph_objs._figure.Figure

optuna.visualization.plot_optimization_history

optuna.visualization.plot_optimization_history(study, *, target=None, target_name='Objective Value', error_bar=False)

Plot optimization history of all trials in a study.

Example

The following code snippet shows how to plot optimization history.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x ** 2 + y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)

fig = optuna.visualization.plot_optimization_history(study)
fig.show()
```

Parameters

• **study** (*Union*[optuna.study.study.Study, *Sequence*[optuna.study.study.Study]]) – A *Study* object whose trials are plotted for their target values. You can pass multiple studies if you want to compare those optimization histories.

• target (Optional [Callable [[optuna.trial._frozen.FrozenTrial], float]]) — A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

- target_name (str) Target's name to display on the axis label and the legend.
- **error_bar** (*bool*) A flag to show the error bar.

Returns A plotly.graph_objs.Figure object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type plotly.graph_objs._figure.Figure

optuna.visualization.plot parallel coordinate

```
optuna.visualization.plot_parallel_coordinate(study, params=None, *, target=None, target_name='Objective Value')
```

Plot the high-dimensional parameter relationships in a study.

Note that, if a parameter contains missing values, a trial with missing values is not plotted.

Example

The following code snippet shows how to plot the high-dimensional parameter relationships.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x ** 2 + y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)

fig = optuna.visualization.plot_parallel_coordinate(study, params=["x", "y"])
fig.show()
```

Parameters

- **study** (optuna.study.study) A *Study* object whose trials are plotted for their target values.
- params (Optional [List[str]]) Parameter list to visualize. The default is all parameters.
- target (Optional[Callable[[optuna.trial._frozen.FrozenTrial], float]])

 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

• target_name (str) – Target's name to display on the axis label and the legend.

Returns A plotly.graph_objs.Figure object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type plotly.graph_objs._figure.Figure

optuna.visualization.plot param importances

```
optuna.visualization.plot_param_importances(study, evaluator=None, params=None, *, target=None, target_name='Objective Value')
```

Plot hyperparameter importances.

Example

The following code snippet shows how to plot hyperparameter importances.

```
def objective(trial):
    x = trial.suggest_int("x", 0, 2)
    y = trial.suggest_float("y", -1.0, 1.0)
    z = trial.suggest_float("z", 0.0, 1.5)
    return x ** 2 + y ** 3 - z ** 4

sampler = optuna.samplers.RandomSampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=100)

fig = optuna.visualization.plot_param_importances(study)
fig.show()
```

See also:

This function visualizes the results of optuna.importance.get_param_importances().

Parameters

- study (optuna.study.study) An optimized study.
- evaluator (Optional [optuna.importance._base.BaseImportanceEvaluator]) An importance evaluator object that specifies which algorithm to base the importance assessment on. Defaults to FanovaImportanceEvaluator.
- params (Optional [List[str]]) A list of names of parameters to assess. If None, all parameters that are present in all of the completed trials are assessed.
- target (Optional[Callable[[optuna.trial._frozen.FrozenTrial], float]])

 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization. For example, to get the hyperparameter importance of the first objective, use target=lambda t: t.values[0] for the target parameter.

• target_name (str) - Target's name to display on the axis label.

Returns A plotly.graph_objs.Figure object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type plotly.graph_objs._figure.Figure

optuna.visualization.plot_pareto_front

optuna.visualization.plot_pareto_front(study, *, target_names=None, include_dominated_trials=True, axis_order=None, constraints_func=None)

Plot the Pareto front of a study.

See also:

Please refer to Multi-objective Optimization with Optuna for the tutorial of the Pareto front visualization.

Example

The following code snippet shows how to plot the Pareto front of a study.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", 0, 5)
    y = trial.suggest_float("y", 0, 3)

    v0 = 4 * x ** 2 + 4 * y ** 2
    v1 = (x - 5) ** 2 + (y - 5) ** 2
    return v0, v1

study = optuna.create_study(directions=["minimize", "minimize"])
study.optimize(objective, n_trials=50)

fig = optuna.visualization.plot_pareto_front(study)
fig.show()
```

Parameters

- **study** (optuna.study.study) A *Study* object whose trials are plotted for their objective values.
- target_names (Optional[List[str]]) Objective name list used as the axis titles. If None is specified, "Objective {objective_index}" is used instead.
- include_dominated_trials (bool) A flag to include all dominated trial's objective values.

- axis_order (Optional [List [int]]) A list of indices indicating the axis order. If None is specified, default order is used.
- constraints_func (Optional[Callable[[optuna.trial._frozen. FrozenTrial], Sequence[float]]]) An optional function that computes the objective constraints. It must take a FrozenTrial and return the constraints. The return value must be a sequence of float s. A value strictly larger than 0 means that a constraint is violated. A value equal to or smaller than 0 is considered feasible. This specification is the same as in, for example, NSGAIISampler.

If given, trials are classified into three categories: feasible and best, feasible but non-best, and infeasible. Categories are shown in different colors. Here, whether a trial is best (on Pareto front) or not is determined ignoring all infeasible trials.

Returns A plotly.graph_objs.Figure object.

Raises ValueError – If the number of objectives of study isn't 2 or 3.

Return type plotly.graph_objs._figure.Figure

Note: Added in v2.4.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.4.0.

optuna.visualization.plot slice

optuna.visualization.plot_slice(study, params=None, *, target=None, target_name='Objective Value')

Plot the parameter relationship as slice plot in a study.

Note that, if a parameter contains missing values, a trial with missing values is not plotted.

Example

The following code snippet shows how to plot the parameter relationship as slice plot.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x ** 2 + y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)

fig = optuna.visualization.plot_slice(study, params=["x", "y"])
fig.show()
```

Parameters

• **study** (optuna.study.study) – A *Study* object whose trials are plotted for their target values.

- params (Optional [List[str]]) Parameter list to visualize. The default is all parameters.
- target (Optional [Callable [[optuna.trial._frozen.FrozenTrial], float]])
 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

• target_name (str) - Target's name to display on the axis label.

Returns A plotly.graph_objs.Figure object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type plotly.graph_objs._figure.Figure

optuna.visualization.is_available

optuna.visualization.is_available()

Returns whether visualization with plotly is available or not.

Note: *visualization* module depends on plotly version 4.0.0 or higher. If a supported version of plotly isn't installed in your environment, this function will return False. In such case, please execute \$ pip install -U plotly>=4.0.0 to install plotly.

Returns True if visualization with plotly is available, False otherwise.

Return type bool

Note: The following optuna.visualization.matplotlib module uses Matplotlib as a backend.

optuna.visualization.matplotlib

Note: The following functions use Matplotlib as a backend.

	D1.441
optuna.visualization.matplotlib.	Plot the parameter relationship as contour plot in a study
plot_contour	with Matplotlib.
optuna.visualization.matplotlib.plot_edf	Plot the objective value EDF (empirical distribution
	function) of a study with Matplotlib.
optuna.visualization.matplotlib.	Plot intermediate values of all trials in a study with Mat-
plot_intermediate_values	plotlib.
optuna.visualization.matplotlib.	Plot optimization history of all trials in a study with Mat-
plot_optimization_history	plotlib.
optuna.visualization.matplotlib.	Plot the high-dimensional parameter relationships in a
plot_parallel_coordinate	study with Matplotlib.
optuna.visualization.matplotlib.	Plot hyperparameter importances with Matplotlib.
plot_param_importances	
optuna.visualization.matplotlib.	Plot the Pareto front of a study.
plot_pareto_front	
optuna.visualization.matplotlib.plot_slice	Plot the parameter relationship as slice plot in a study
	with Matplotlib.
optuna.visualization.matplotlib.	Returns whether visualization with Matplotlib is avail-
is_available	able or not.

optuna.visualization.matplotlib.plot_contour

```
optuna.visualization.matplotlib.plot_contour(study, params=None, *, target=None, target_name='Objective Value')
```

Plot the parameter relationship as contour plot in a study with Matplotlib.

Note that, if a parameter contains missing values, a trial with missing values is not plotted.

See also:

Please refer to optuna.visualization.plot_contour() for an example.

Warning: Output figures of this Matplotlib-based *plot_contour()* function would be different from those of the Plotly-based *plot_contour()*.

Example

The following code snippet shows how to plot the parameter relationship as contour plot.


```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x ** 2 + y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=30)
```

(continues on next page)

optuna.visualization.matplotlib.plot_contour(study, params=["x", "y"])



Parameters

- **study** (optuna.study.study) A *Study* object whose trials are plotted for their target values.
- params (Optional [List[str]]) Parameter list to visualize. The default is all parameters
- target (Optional[Callable[[optuna.trial._frozen.FrozenTrial], float]])

 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

• target_name (str) - Target's name to display on the color bar.

Returns A matplotlib.axes.Axes object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type matplotlib.axes._axes.Axes

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

optuna.visualization.matplotlib.plot_edf

optuna.visualization.matplotlib.plot_edf(study, *, target=None, target_name='Objective Value')

Plot the objective value EDF (empirical distribution function) of a study with Matplotlib.

Note that only the complete trials are considered when plotting the EDF.

See also:

Please refer to <code>optuna.visualization.plot_edf()</code> for an example, where this function can be replaced with it

Note: Please refer to matplotlib.pyplot.legend to adjust the style of the generated legend.


Example

The following code snippet shows how to plot EDF.

```
import math
import optuna
def ackley(x, y):
    a = 20 * math.exp(-0.2 * math.sqrt(0.5 * (x ** 2 + y ** 2)))
   b = math.exp(0.5 * (math.cos(2 * math.pi * x) + math.cos(2 * math.pi * y)))
   return -a - b + math.e + 20
def objective(trial, low, high):
   x = trial.suggest_float("x", low, high)
   y = trial.suggest_float("y", low, high)
   return ackley(x, y)
sampler = optuna.samplers.RandomSampler(seed=10)
# Widest search space.
study0 = optuna.create_study(study_name="x=[0,5)", y=[0,5)", sampler=sampler)
study0.optimize(lambda t: objective(t, 0, 5), n_trials=500)
# Narrower search space.
study1 = optuna.create_study(study_name="x=[0,4), y=[0,4)", sampler=sampler)
study1.optimize(lambda t: objective(t, 0, 4), n_trials=500)
# Narrowest search space but it doesn't include the global optimum point.
```

(continues on next page)

```
study2 = optuna.create_study(study_name="x=[1,3), y=[1,3)", sampler=sampler)
study2.optimize(lambda t: objective(t, 1, 3), n_trials=500)
optuna.visualization.matplotlib.plot_edf([study0, study1, study2])
```



Parameters

- **study** (*Union*[optuna.study.study.Study, *Sequence*[optuna.study.study.Study]]) A target *Study* object. You can pass multiple studies if you want to compare those EDFs.
- target (Optional[Callable[[optuna.trial._frozen.FrozenTrial], float]])

 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

• **target_name** (*str*) – Target's name to display on the axis label.

Returns A matplotlib.axes.Axes object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type matplotlib.axes._axes.Axes

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

optuna.visualization.matplotlib.plot_intermediate_values

```
optuna.visualization.matplotlib.plot_intermediate_values(study)
```

Plot intermediate values of all trials in a study with Matplotlib.

Note: Please refer to matplotlib.pyplot.legend to adjust the style of the generated legend.


Example

The following code snippet shows how to plot intermediate values.

```
import optuna
def f(x):
   return (x - 2) ** 2
def df(x):
   return 2 * x - 4
def objective(trial):
   lr = trial.suggest_float("lr", 1e-5, 1e-1, log=True)
   x = 3
    for step in range(128):
       y = f(x)
        trial.report(y, step=step)
        if trial.should_prune():
            raise optuna.TrialPruned()
        gy = df(x)
        x -= gy * 1r
   return y
sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=16)
```

(continues on next page)

optuna.visualization.matplotlib.plot_intermediate_values(study)



See also:

Please refer to optuna.visualization.plot_intermediate_values() for an example.

Parameters study (optuna.study.study) – A *Study* object whose trials are plotted for their intermediate values.

Returns A matplotlib.axes.Axes object.

Return type matplotlib.axes._axes.Axes

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

optuna.visualization.matplotlib.plot_optimization_history

```
optuna.visualization.matplotlib.plot_optimization_history(study, *, target=None, target_name='Objective Value', error_bar=False)
```

Plot optimization history of all trials in a study with Matplotlib.

See also:

Please refer to optuna.visualization.plot_optimization_history() for an example.

Example

The following code snippet shows how to plot optimization history.

```
import optuna
import matplotlib.pyplot as plt

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x ** 2 + y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)

optuna.visualization.matplotlib.plot_optimization_history(study)
plt.tight_layout()
```

Note: You need to adjust the size of the plot by yourself using plt.tight_layout() or plt. savefig(IMAGE_NAME, bbox_inches='tight').

Parameters


- **study** (*Union*[optuna.study.study.Study, *Sequence*[optuna.study.study.Study]]) A *Study* object whose trials are plotted for their target values. You can pass multiple studies if you want to compare those optimization histories.
- target (Optional [Callable [[optuna.trial._frozen.FrozenTrial], float]]) A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

- target_name (str) Target's name to display on the axis label and the legend.
- **error_bar** (*bool*) A flag to show the error bar.

Returns A matplotlib.axes.Axes object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.



Return type matplotlib.axes._axes.Axes

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

optuna.visualization.matplotlib.plot_parallel_coordinate

```
optuna.visualization.matplotlib.plot_parallel_coordinate(study, params=None, *, target=None, target_name='Objective Value')
```

Plot the high-dimensional parameter relationships in a study with Matplotlib.

Note that, if a parameter contains missing values, a trial with missing values is not plotted.

See also:

Please refer to optuna.visualization.plot_parallel_coordinate() for an example.

Example

The following code snippet shows how to plot the high-dimensional parameter relationships.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x ** 2 + y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)

optuna.visualization.matplotlib.plot_parallel_coordinate(study, params=["x", "y"])
```

Parameters


- **study** (optuna.study.study) A *Study* object whose trials are plotted for their target values.
- params (Optional [List[str]]) Parameter list to visualize. The default is all parameters.
- target (Optional[Callable[[optuna.trial._frozen.FrozenTrial], float]])

 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

• target_name (str) – Target's name to display on the axis label and the legend.

Returns A matplotlib.axes.Axes object.



Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type matplotlib.axes._axes.Axes

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

optuna.visualization.matplotlib.plot param importances

```
optuna.visualization.matplotlib.plot_param_importances(study, evaluator=None, params=None, *, target=None, target_name='Objective Value')
```

Plot hyperparameter importances with Matplotlib.

See also:

Please refer to optuna.visualization.plot_param_importances() for an example.

Example


The following code snippet shows how to plot hyperparameter importances.

```
def objective(trial):
    x = trial.suggest_int("x", 0, 2)
    y = trial.suggest_float("y", -1.0, 1.0)
    z = trial.suggest_float("z", 0.0, 1.5)
    return x ** 2 + y ** 3 - z ** 4

sampler = optuna.samplers.RandomSampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=100)
optuna.visualization.matplotlib.plot_param_importances(study)
```

Parameters

- **study** (optuna.study.study) An optimized study.
- evaluator (Optional [optuna.importance._base.BaseImportanceEvaluator]) An importance evaluator object that specifies which algorithm to base the importance assessment on. Defaults to FanovaImportanceEvaluator.
- params (Optional [List[str]]) A list of names of parameters to assess. If None, all parameters that are present in all of the completed trials are assessed.
- target (Optional [Callable [[optuna.trial._frozen.FrozenTrial], float]])
 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.



Note: Specify this argument if study is being used for multi-objective optimization. For example, to get the hyperparameter importance of the first objective, use target=lambda t: t.values[0] for the target parameter.

• target_name (str) - Target's name to display on the axis label.

Returns A matplotlib.axes.Axes object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type matplotlib.axes._axes.Axes

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

optuna.visualization.matplotlib.plot_pareto_front

```
optuna.visualization.matplotlib.plot_pareto_front(study, *, target_names=None, include_dominated_trials=True, axis_order=None, targets=None)
```

Plot the Pareto front of a study.

See also:

Please refer to optuna.visualization.plot_pareto_front() for an example.

Example

The following code snippet shows how to plot the Pareto front of a study.

```
import optuna

def objective(trial):
    x = trial.suggest_float("x", 0, 5)
    y = trial.suggest_float("y", 0, 3)


    v0 = 4 * x ** 2 + 4 * y ** 2
    v1 = (x - 5) ** 2 + (y - 5) ** 2
    return v0, v1

study = optuna.create_study(directions=["minimize", "minimize"])
study.optimize(objective, n_trials=50)

optuna.visualization.matplotlib.plot_pareto_front(study)
```

Parameters

• **study** (optuna.study.study) – A *Study* object whose trials are plotted for their objective values.



- target_names (Optional [List[str]]) Objective name list used as the axis titles. If None is specified, "Objective {objective_index}" is used instead.
- include_dominated_trials (bool) A flag to include all dominated trial's objective
 values.
- axis_order (Optional [List[int]]) A list of indices indicating the axis order. If None is specified, default order is used.

Warning: Deprecated in v3.0.0. This feature will be removed in the future. The removal of this feature is currently scheduled for v5.0.0, but this schedule is subject to change. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

• targets (Optional[Callable[[optuna.trial._frozen.FrozenTrial], Sequence[float]]]) — A function that returns a tuple of target values to display. The argument to this function is FrozenTrial.

Note: Added in v3.0.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v3.0.0.

Returns A matplotlib.axes.Axes object.

Raises

- ValueError If targets is None when your objective studies have more than 3 objectives.
- **ValueError** If targets returns something other than sequence.
- **ValueError** If the number of target values to display isn't 2 or 3.
- ValueError If targets is specified for empty studies and target_names is None.
- ValueError If using both targets and axis_order.

Return type matplotlib.axes._axes.Axes

Note: Added in v2.8.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.8.0.

optuna.visualization.matplotlib.plot slice

```
optuna.visualization.matplotlib.plot_slice(study, params=None, *, target=None, target_name='Objective Value')
```

Plot the parameter relationship as slice plot in a study with Matplotlib.

See also:

Please refer to $optuna.visualization.plot_slice()$ for an example.

Example


The following code snippet shows how to plot the parameter relationship as slice plot.

```
def objective(trial):
    x = trial.suggest_float("x", -100, 100)
    y = trial.suggest_categorical("y", [-1, 0, 1])
    return x ** 2 + y

sampler = optuna.samplers.TPESampler(seed=10)
study = optuna.create_study(sampler=sampler)
study.optimize(objective, n_trials=10)

optuna.visualization.matplotlib.plot_slice(study, params=["x", "y"])
```

Slice Plot



Parameters

• **study** (optuna.study.study) – A *Study* object whose trials are plotted for their target values.

- params (Optional [List[str]]) Parameter list to visualize. The default is all parameters.
- target (Optional [Callable [[optuna.trial._frozen.FrozenTrial], float]])
 A function to specify the value to display. If it is None and study is being used for single-objective optimization, the objective values are plotted.

Note: Specify this argument if study is being used for multi-objective optimization.

• target_name (str) - Target's name to display on the axis label.

Returns A matplotlib.axes.Axes object.

Raises ValueError – If target is None and study is being used for multi-objective optimization.

Return type matplotlib.axes._axes.Axes

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

optuna.visualization.matplotlib.is available

optuna.visualization.matplotlib.is_available()

Returns whether visualization with Matplotlib is available or not.

Note: *matplotlib* module depends on Matplotlib version 3.0.0 or higher. If a supported version of Matplotlib isn't installed in your environment, this function will return False. In such a case, please execute \$ pip install -U matplotlib>=3.0.0 to install Matplotlib.

Returns True if visualization with Matplotlib is available, False otherwise.

Return type bool

Note: Added in v2.2.0 as an experimental feature. The interface may change in newer versions without prior notice. See https://github.com/optuna/optuna/releases/tag/v2.2.0.

See also:

The 5. Quick Visualization for Hyperparameter Optimization Analysis tutorial provides use-cases with examples.

6.4 FAQ

- Can I use Optuna with X? (where X is your favorite ML library)
- How to define objective functions that have own arguments?
- Can I use Optuna without remote RDB servers?
- How can I save and resume studies?
- How to suppress log messages of Optuna?
- How to save machine learning models trained in objective functions?
- *How can I obtain reproducible optimization results?*
- How are exceptions from trials handled?
- How are NaNs returned by trials handled?
- What happens when I dynamically alter a search space?
- How can I use two GPUs for evaluating two trials simultaneously?
- *How can I test my objective functions?*
- How do I avoid running out of memory (OOM) when optimizing studies?
- How can I output a log only when the best value is updated?
- How do I suggest variables which represent the proportion, that is, are in accordance with Dirichlet distribution?
- How can I optimize a model with some constraints?
- How can I parallelize optimization?
 - 1. Multi-threading parallelization with a single node
 - 2. Multi-processing parallelization with single node
 - 3. Multi-processing parallelization with multiple nodes
- Can I monitor trials and make them failed automatically when they are killed unexpectedly?

6.4.1 Can I use Optuna with X? (where X is your favorite ML library)

Optuna is compatible with most ML libraries, and it's easy to use Optuna with those. Please refer to examples.

6.4.2 How to define objective functions that have own arguments?

There are two ways to realize it.

First, callable classes can be used for that purpose as follows:

```
import optuna

class Objective(object):
    def __init__(self, min_x, max_x):
```

(continues on next page)

```
# Hold this implementation specific arguments as the fields of the class.
self.min_x = min_x
self.max_x = max_x

def __call__(self, trial):
    # Calculate an objective value by using the extra arguments.
    x = trial.suggest_float("x", self.min_x, self.max_x)
    return (x - 2) ** 2
# Execute an optimization by using an `Objective` instance.
study = optuna.create_study()
study.optimize(Objective(-100, 100), n_trials=100)
```

Second, you can use lambda or functools.partial for creating functions (closures) that hold extra arguments. Below is an example that uses lambda:

```
import optuna

# Objective function that takes three arguments.
def objective(trial, min_x, max_x):
    x = trial.suggest_float("x", min_x, max_x)
    return (x - 2) ** 2

# Extra arguments.
min_x = -100
max_x = 100

# Execute an optimization by using the above objective function wrapped by `lambda`.
study = optuna.create_study()
study.optimize(lambda trial: objective(trial, min_x, max_x), n_trials=100)
```

Please also refer to sklearn_addtitional_args.py example, which reuses the dataset instead of loading it in each trial execution.

6.4.3 Can I use Optuna without remote RDB servers?

Yes, it's possible.

In the simplest form, Optuna works with in-memory storage:

```
study = optuna.create_study()
study.optimize(objective)
```

If you want to save and resume studies, it's handy to use SQLite as the local storage:

```
study = optuna.create_study(study_name="foo_study", storage="sqlite:///example.db")
study.optimize(objective) # The state of `study` will be persisted to the local SQLite_
file.
```

Please see Saving/Resuming Study with RDB Backend for more details.

6.4. FAQ 309

6.4.4 How can I save and resume studies?

There are two ways of persisting studies, which depend if you are using in-memory storage (default) or remote databases (RDB). In-memory studies can be saved and loaded like usual Python objects using pickle or joblib. For example, using joblib:

```
study = optuna.create_study()
joblib.dump(study, "study.pkl")
```

And to resume the study:

```
study = joblib.load("study.pkl")
print("Best trial until now:")
print(" Value: ", study.best_trial.value)
print(" Params: ")
for key, value in study.best_trial.params.items():
    print(f" {key}: {value}")
```

Note that Optuna does not support saving/reloading across different Optuna versions with pickle. To save/reload a study across different Optuna versions, please use RDBs and upgrade storage schema if necessary. If you are using RDBs, see *Saving/Resuming Study with RDB Backend* for more details.

6.4.5 How to suppress log messages of Optuna?

By default, Optuna shows log messages at the optuna.logging.INFO level. You can change logging levels by using optuna.logging.set_verbosity().

For instance, you can stop showing each trial result as follows:

```
optuna.logging.set_verbosity(optuna.logging.WARNING)
study = optuna.create_study()
study.optimize(objective)
# Logs like '[I 2020-07-21 13:41:45,627] Trial 0 finished with value:...' are disabled.
```

Please refer to optuna.logging for further details.

6.4.6 How to save machine learning models trained in objective functions?

Optuna saves hyperparameter values with its corresponding objective value to storage, but it discards intermediate objects such as machine learning models and neural network weights. To save models or weights, please use features of the machine learning library you used.

We recommend saving *optuna.trial.Trial.number* with a model in order to identify its corresponding trial. For example, you can save SVM models trained in the objective function as follows:

```
def objective(trial):
    svc_c = trial.suggest_float("svc_c", 1e-10, 1e10, log=True)
    clf = sklearn.svm.SVC(C=svc_c)
    clf.fit(X_train, y_train)

# Save a trained model to a file.
    with open("{}.pickle".format(trial.number), "wb") as fout:
```

(continues on next page)

```
pickle.dump(clf, fout)
return 1.0 - accuracy_score(y_valid, clf.predict(X_valid))

study = optuna.create_study()
study.optimize(objective, n_trials=100)

# Load the best model.
with open("{}.pickle".format(study.best_trial.number), "rb") as fin:
    best_clf = pickle.load(fin)
print(accuracy_score(y_valid, best_clf.predict(X_valid)))
```

6.4.7 How can I obtain reproducible optimization results?

To make the parameters suggested by Optuna reproducible, you can specify a fixed random seed via seed argument of RandomSampler or TPESampler as follows:

```
sampler = TPESampler(seed=10) # Make the sampler behave in a deterministic way.
study = optuna.create_study(sampler=sampler)
study.optimize(objective)
```

However, there are two caveats.

First, when optimizing a study in distributed or parallel mode, there is inherent non-determinism. Thus it is very difficult to reproduce the same results in such condition. We recommend executing optimization of a study sequentially if you would like to reproduce the result.

Second, if your objective function behaves in a non-deterministic way (i.e., it does not return the same value even if the same parameters were suggested), you cannot reproduce an optimization. To deal with this problem, please set an option (e.g., random seed) to make the behavior deterministic if your optimization target (e.g., an ML library) provides it.

6.4.8 How are exceptions from trials handled?

Trials that raise exceptions without catching them will be treated as failures, i.e. with the FAIL status.

By default, all exceptions except *TrialPruned* raised in objective functions are propagated to the caller of *optimize()*. In other words, studies are aborted when such exceptions are raised. It might be desirable to continue a study with the remaining trials. To do so, you can specify in *optimize()* which exception types to catch using the catch argument. Exceptions of these types are caught inside the study and will not propagate further.

You can find the failed trials in log messages.

```
[W 2018-12-07 16:38:36,889] Setting status of trial#0 as TrialState.FAIL because of \ the following error: ValueError('A sample error in objective.')
```

You can also find the failed trials by checking the trial states as follows:

```
study.trials_dataframe()
```

6.4. FAQ 311

num-	state	value	 param	s system_attrs
ber				
0	Trial-		 0	Setting status of trial#0 as TrialState.FAIL because of the following
	State.FAIL			error: ValueError('A test error in objective.')
1	Trial-	1269	 1	
	State.COMPLE	ΤЕ		

See also:

The catch argument in optimize().

6.4.9 How are NaNs returned by trials handled?

Trials that return NaN (float('nan')) are treated as failures, but they will not abort studies.

Trials which return NaN are shown as follows:

[W 2018-12-07 16:41:59,000] Setting status of trial#2 as TrialState.FAIL because the \setminus objective **function** returned nan.

6.4.10 What happens when I dynamically alter a search space?

Since parameters search spaces are specified in each call to the suggestion API, e.g. <code>suggest_float()</code> and <code>suggest_int()</code>, it is possible to, in a single study, alter the range by sampling parameters from different search spaces in different trials. The behavior when altered is defined by each sampler individually.

Note: Discussion about the TPE sampler. https://github.com/optuna/optuna/issues/822

6.4.11 How can I use two GPUs for evaluating two trials simultaneously?

If your optimization target supports GPU (CUDA) acceleration and you want to specify which GPU is used in your script, main.py, the easiest way is to set CUDA_VISIBLE_DEVICES environment variable:

```
# On a terminal.
#
# Specify to use the first GPU, and run an optimization.
$ export CUDA_VISIBLE_DEVICES=0
$ python main.py
# On another terminal.
#
# Specify to use the second GPU, and run another optimization.
$ export CUDA_VISIBLE_DEVICES=1
$ python main.py
```

Please refer to CUDA C Programming Guide for further details.

6.4.12 How can I test my objective functions?

When you test objective functions, you may prefer fixed parameter values to sampled ones. In that case, you can use FixedTrial, which suggests fixed parameter values based on a given dictionary of parameters. For instance, you can input arbitrary values of x and y to the objective function x + y as follows:

```
def objective(trial):
    x = trial.suggest_float("x", -1.0, 1.0)
    y = trial.suggest_int("y", -5, 5)
    return x + y

objective(FixedTrial({"x": 1.0, "y": -1})) # 0.0
objective(FixedTrial({"x": -1.0, "y": -4})) # -5.0
```

Using FixedTrial, you can write unit tests as follows:

```
# A test function of pytest
def test_objective():
    assert 1.0 == objective(FixedTrial({"x": 1.0, "y": 0}))
    assert -1.0 == objective(FixedTrial({"x": 0.0, "y": -1}))
    assert 0.0 == objective(FixedTrial({"x": -1.0, "y": 1}))
```

6.4.13 How do I avoid running out of memory (OOM) when optimizing studies?

If the memory footprint increases as you run more trials, try to periodically run the garbage collector. Specify gc_after_trial to True when calling optimize() or call gc.collect() inside a callback.

```
def objective(trial):
    x = trial.suggest_float("x", -1.0, 1.0)
    y = trial.suggest_int("y", -5, 5)
    return x + y

study = optuna.create_study()
study.optimize(objective, n_trials=10, gc_after_trial=True)

# `gc_after_trial=True` is more or less identical to the following.
study.optimize(objective, n_trials=10, callbacks=[lambda study, trial: gc.collect()])
```

There is a performance trade-off for running the garbage collector, which could be non-negligible depending on how fast your objective function otherwise is. Therefore, gc_after_trial is False by default. Note that the above examples are similar to running the garbage collector inside the objective function, except for the fact that gc.collect() is called even when errors, including *TrialPruned* are raised.

Note: ChainerMNStudy does currently not provide gc_after_trial nor callbacks for optimize(). When using this class, you will have to call the garbage collector inside the objective function.

6.4. FAQ 313

6.4.14 How can I output a log only when the best value is updated?

Here's how to replace the logging feature of optuna with your own logging callback function. The implemented callback can be passed to <code>optimize()</code>. Here's an example:

```
import optuna
# Turn off optuna log notes.
optuna.logging.set_verbosity(optuna.logging.WARN)
def objective(trial):
   x = trial.suggest_float("x", 0, 1)
   return x ** 2
def logging_callback(study, frozen_trial):
   previous_best_value = study.user_attrs.get("previous_best_value", None)
    if previous_best_value != study.best_value:
        study.set_user_attr("previous_best_value", study.best_value)
        print(
            "Trial {} finished with best value: {} and parameters: {}. ".format(
            frozen_trial.number,
            frozen_trial.value,
            frozen_trial.params,
            )
        )
study = optuna.create_study()
study.optimize(objective, n_trials=100, callbacks=[logging_callback])
```

Note that this callback may show incorrect values when you try to optimize an objective function with n_jobs!=1 (or other forms of distributed optimization) due to its reads and writes to storage that are prone to race conditions.

6.4.15 How do I suggest variables which represent the proportion, that is, are in accordance with Dirichlet distribution?

When you want to suggest n variables which represent the proportion, that is, p[0], p[1], ..., p[n-1] which satisfy $0 \le p[k] \le 1$ for any k and p[0] + p[1] + ... + p[n-1] = 1, try the below. For example, these variables can be used as weights when interpolating the loss functions. These variables are in accordance with the flat Dirichlet distribution.

```
import numpy as np
import matplotlib.pyplot as plt
import optuna

def objective(trial):
    n = 5
    x = []
    for i in range(n):
```

(continues on next page)

314

```
x.append(- np.log(trial.suggest_float(f"x_{i}", 0, 1)))
   p = []
   for i in range(n):
       p.append(x[i] / sum(x))
   for i in range(n):
        trial.set_user_attr(f"p_{i}", p[i])
   return 0
study = optuna.create_study(sampler=optuna.samplers.RandomSampler())
study.optimize(objective, n_trials=1000)
n = 5
p = []
for i in range(n):
   p.append([trial.user_attrs[f"p_{i}"] for trial in study.trials])
axes = plt.subplots(n, n, figsize=(20, 20))[1]
for i in range(n):
    for j in range(n):
        axes[j][i].scatter(p[i], p[j], marker=".")
        axes[j][i].set_xlim(0, 1)
        axes[j][i].set_ylim(0, 1)
        axes[j][i].set_xlabel(f"p_{i}")
        axes[j][i].set_ylabel(f"p_{j}")
plt.savefig("sampled_ps.png")
```

This method is justified in the following way: First, if we apply the transformation $x=-\log(u)$ to the variable u sampled from the uniform distribution Uni(0,1) in the interval [0,1], the variable x will follow the exponential distribution Exp(1) with scale parameter 1. Furthermore, for n variables x[0],...,x[n-1] that follow the exponential distribution of scale parameter 1 independently, normalizing them with $p[i]=x[i]/\sum_i x[i]$, the vector p follows the Dirichlet distribution $Dir(\alpha)$ of scale parameter $\alpha=(1,...,1)$. You can verify the transformation by calculating the elements of the Jacobian.

6.4.16 How can I optimize a model with some constraints?

When you want to optimize a model with constraints, you can use the following classes, NSGAIISampler or BoTorchSampler. The following example is a benchmark of Binh and Korn function, a multi-objective optimization, with constraints using NSGAIISampler. This one has two constraints $c_0 = (x-5)^2 + y^2 - 25 \le 0$ and $c_1 = -(x-8)^2 - (y+3)^2 + 7.7 \le 0$ and finds the optimal solution satisfying these constraints.

```
def objective(trial):
    # Binh and Korn function with constraints.
    x = trial.suggest_float("x", -15, 30)
    y = trial.suggest_float("y", -15, 30)
```

(continues on next page)

6.4. FAQ 315

```
# Constraints which are considered feasible if less than or equal to zero.
    # The feasible region is basically the intersection of a circle centered at (x=5,...)
\rightarrow v=0)
    # and the complement to a circle centered at (x=8, y=-3).
   c0 = (x - 5) ** 2 + y ** 2 - 25
   c1 = -((x - 8) ** 2) - (y + 3) ** 2 + 7.7
    # Store the constraints as user attributes so that they can be restored after.
→optimization.
   trial.set_user_attr("constraint", (c0, c1))
   v0 = 4 * x ** 2 + 4 * y ** 2
   v1 = (x - 5) ** 2 + (y - 5) ** 2
   return v0, v1
def constraints(trial):
   return trial.user_attrs["constraint"]
sampler = optuna.samplers.NSGAIISampler(constraints_func=constraints)
study = optuna.create_study(
    directions=["minimize", "minimize"],
    sampler=sampler,
study.optimize(objective, n_trials=32, timeout=600)
print("Number of finished trials: ", len(study.trials))
print("Pareto front:")
trials = sorted(study.best_trials, key=lambda t: t.values)
for trial in trials:
   print(" Trial#{}".format(trial.number))
   print(
             Values: Values={}, Constraint={}".format(
            trial.values, trial.user_attrs["constraint"][0]
        )
   )
               Params: {}".format(trial.params))
   print("
```

If you are interested in the exmaple for BoTorchSampler, please refer to this sample code.

There are two kinds of constrained optimizations, one with soft constraints and the other with hard constraints. Soft constraints do not have to be satisfied, but an objective function is penalized if they are unsatisfied. On the other hand, hard constraints must be satisfied.

Optuna is adopting the soft one and **DOES NOT** support the hard one. In other words, Optuna **DOES NOT** have built-in samplers for the hard constraints.

6.4.17 How can I parallelize optimization?

The variations of parallelization are in the following three cases.

- 1. Multi-threading parallelization with single node
- 2. Multi-processing parallelization with single node
- 3. Multi-processing parallelization with multiple nodes

1. Multi-threading parallelization with a single node

Parallelization can be achieved by setting the argument n_jobs in optuna.study.Study.optimize(). However, the python code will not be faster due to GIL because optuna.study.Study.optimize() with n_jobs!=1 uses multi-threading.

While optimizing, it will be faster in limited situations, such as waiting for other server requests or C/C++ processing with numpy, etc., but it will not be faster in other cases.

For more information about 1., see APIReference.

2. Multi-processing parallelization with single node

This can be achieved by using file-based RDBs (such as SQLite) and client/server RDBs (such as PostgreSQL and MySQL). However, if you are in the environment where you can not install an RDB, you can not run multi-processing parallelization with single node. When you really want to do it, please request it as a GitHub issue. If we receive a lot of requests, we may provide a solution for it.

For more information about 2., see TutorialEasyParallelization.

3. Multi-processing parallelization with multiple nodes

This can be achieved by using client/server RDBs (such as PostgreSQL and MySQL). However, if you are in the environment where you can not install a client/server RDB, you can not run multi-processing parallelization with multiple nodes.

For more information about 3., see TutorialEasyParallelization.

6.4.18 Can I monitor trials and make them failed automatically when they are killed unexpectedly?

Note: Heartbeat mechanism is experimental. API would change in the future.

A process running a trial could be killed unexpectedly, typically by a job scheduler in a cluster environment. If trials are killed unexpectedly, they will be left on the storage with their states *RUNNING* until we remove them or update their state manually. For such a case, Optuna supports monitoring trials using heartbeat mechanism. Using heartbeat, if a process running a trial is killed unexpectedly, Optuna will automatically change the state of the trial that was running on that process to *FAIL* from *RUNNING*.

import optuna

def objective(trial):

(continues on next page)

6.4. FAQ 317

Note: The heartbeat is supposed to be used with *optimize()*. If you use *ask()* and *tell()*, please change the state of the killed trials by calling *tell()* explicitly.

You can also execute a callback function to process the failed trial. Optuna provides a callback to retry failed trials as <code>RetryFailedTrialCallback</code>. Note that a callback is invoked at a beginning of each trial, which means <code>RetryFailedTrialCallback</code> will retry failed trials when a new trial starts to evaluate.

```
import optuna
from optuna.storages import RetryFailedTrialCallback

storage = optuna.storages.RDBStorage(
    url="sqlite:///:memory:",
    heartbeat_interval=60,
    grace_period=120,
    failed_trial_callback=RetryFailedTrialCallback(max_retry=3),
)

study = optuna.create_study(storage=storage)
```

CHAPTER

SEVEN

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

0

```
optuna, 61
optuna.cli,67
optuna.distributions, 73
optuna.exceptions, 84
optuna.importance, 86
optuna.integration, 90
optuna.logging, 136
optuna.multi_objective, 141
optuna.multi_objective.samplers, 141
optuna.multi_objective.study, 150
optuna.multi_objective.trial, 155
optuna.multi_objective.visualization, 160
optuna.pruners, 162
optuna.samplers, 175
optuna.samplers.nsgaii, 210
optuna.storages, 218
optuna.study, 242
optuna.trial, 262
optuna.visualization, 281
optuna.visualization.matplotlib, 290
```

322 Python Module Index

INDEX

Symbols	search-space
debug	optuna-ask command line option, 69
optuna command line option, 68	skip-if-exists
direction	optuna-create-study command line option,
optuna-ask command line option, 68	70
optuna-create-study command line option,	skip-if-finished
70	optuna-tell command line option,72
directions	state
optuna-ask command line option, 68	optuna-tell command line option,72
optuna-create-study command line option,	storage
70	optuna command line option, 68
flatten	study
optuna-ask command line option, 69	optuna-study-optimize command line
optuna-best-trial command line option, 69	option, 71
optuna-best-trials command line option,	optuna-study-set-user-attr command line
69	option, 71
optuna-studies command line option, 70	study-name
optuna-trials command line option, 72	optuna-ask command line option,68
format	optuna-best-trial command line option, 69
optuna-ask command line option, 69	optuna-best-trials command line option,
optuna-best-trial command line option, 69	69
optuna-best-trials command line option,	optuna-create-study command line option,
69	70
optuna-studies command line option, 70	optuna-delete-study command line option,
optuna-trials command line option, 72	70
key	optuna-study-optimize command line
optuna-study-set-user-attr command line	option, 71
option, 72	optuna-study-set-user-attr command line
log-file	option, 71
optuna command line option, 68	optuna-tell command line option,72
n-jobs	optuna-trials command line option,72
optuna-study-optimize command line	timeout
option, 71	optuna-study-optimize command line
n-trials	option, 71
optuna-study-optimize command line	trial-number
option, 71	optuna-tell command line option,72
quiet	value
optuna command line option, 68	optuna-study-set-user-attr command line
sampler	option, 72
optuna-ask command line option, 68	values
sampler-kwargs	optuna-tell command line option, 72
optuna-ask command line option, 69	verbose

optuna command line option, 68version	AllenNLPPruningCallback (class in optuna.integration), 92
optuna command line option, 68	ask() (optuna.study.Study method), 245
optuna-ask command line option, 69	В
optuna-best-trial command line option, 69 optuna-best-trials command line option, 69	BaseCrossover (class in optuna.samplers.nsgaii), 211 BaseMultiObjectiveSampler (class in optuna.multi_objective.samplers), 141
optuna-studies command line option, 70 optuna-trials command line option, 72 -k	BasePruner (class in optuna.pruners), 162 BaseSampler (class in optuna.samplers), 176 best_estimator_ (op-
optuna-study-set-user-attr command line option, 72	tuna.integration.OptunaSearchCV attribute), 126
-q optuna command line option, 68 -v	best_index_ (optuna.integration.OptunaSearchCV property), 128 best_params(optuna.integration.lightgbm.LightGBMTuner
optuna command line option, 68 optuna-study-set-user-attr command line option, 72	property), 107 best_params (optuna.integration.lightgbm.LightGBMTunerCV property), 110
4	best_params (optuna.study.Study property), 246 best_params_ (optuna.integration.OptunaSearchCV
add_trial() (optuna.study.Study method), 243 add_trials() (optuna.study.Study method), 244 after_iteration() (op-	property), 128 best_score (optuna.integration.lightgbm.LightGBMTuner property), 107
tuna.integration.CatBoostPruningCallback method), 99	best_score (optuna.integration.lightgbm.LightGBMTunerCV property), 110
after_trial() (optuna.integration.BoTorchSampler method), 95	best_score_ (optuna.integration.OptunaSearchCV property), 128
after_trial() (optuna.integration.CmaEsSampler method), 119	best_trial (optuna.study.Study property), 246 best_trial (optuna.study.StudySummary attribute), 261
after_trial() (optuna.integration.PyCmaSampler method), 117	best_trial_ (optuna.integration.OptunaSearchCV property), 128
after_trial() (optuna.integration.SkoptSampler method), 132	best_trials (optuna.study.Study property), 246 best_value (optuna.study.Study property), 246
after_trial() (optuna.samplers.BaseSampler method), 178	213
method), 193	BoTorchSampler (class in optuna.integration), 93
after_trial() (optuna.samplers.GridSampler method), 181 after_trial() (optuna.samplers.MOTPESampler	calculate() (optuna.samplers.IntersectionSearchSpace
method), 203 after_trial() (optuna.samplers.NSGAIISampler (optuna.samplers.NSGAIISampler	method), 210 CatalystPruningCallback (class in optuna.integration), 98
method), 199 after_trial() (optuna.samplers.PartialFixedSampler	CatBoostPruningCallback (class in optuna.integration), 99
method), 196 after_trial() (optuna.samplers.QMCSampler method), 207	CategoricalDistribution (class in optuna.distributions), 83
after_trial() (optuna.samplers.RandomSampler method), 184	ChainerMNStudy (class in optuna.integration), 100 ChainerPruningExtension (class in optuna.integration), 100
after_trial() (optuna.samplers.TPESampler method), 188	check_distribution_compatibility() (in module optuna.distributions), 84
AllenNLPExecutor (class in optuna.integration), 91	check_pruned() (optuna.integration.CatBoostPruningCallback method), 100

check_trial_is_updatable() (op- tuna.storages.RDBStorage method), 221	<pre>datetime_start (optuna.trial.FrozenTrial attribute),</pre>
check_trial_is_updatable() (op-	datetime_start (optuna.trial.Trial property), 263
tuna.storages.RedisStorage method), 232	decision_function (op-
choices (optuna.distributions.CategoricalDistribution	tuna.integration.OptunaSearchCV property),
attribute), 83	128
classes_ (optuna.integration.OptunaSearchCV prop-	<pre>delete_study() (in module optuna), 64</pre>
erty), 128	<pre>delete_study() (in module optuna.study), 257</pre>
CLIUsageError, 86	delete_study() (optuna.storages.RDBStorage
CmaEsSampler (class in optuna.integration), 119	method), 221
CmaEsSampler (class in optuna.samplers), 191	delete_study() (optuna.storages.RedisStorage
COMPLETE (optuna.trial.TrialState attribute), 279	method), 232
copy_study() (in module optuna), 65	direction (optuna.study.Study property), 247
copy_study() (in module optuna.study), 257	direction (optuna.study.StudySummary attribute), 261
create_new_study() (optuna.storages.RDBStorage	directions (optuna.multi_objective.study.MultiObjectiveStudy
method), 221	property), 151
create_new_study() (optuna.storages.RedisStorage method), 232	directions (optuna.study.Study property), 247 directions (optuna.study.StudySummary attribute), 261
create_new_trial() (optuna.storages.RDBStorage	disable_default_handler() (in module op-
method), 221	tuna.logging), 138
create_new_trial() (optuna.storages.RedisStorage	disable_propagation() (in module optuna.logging),
method), 232	139
create_study() (in module optuna), 62	DiscreteUniformDistribution (class in op-
create_study() (in module op-	tuna.distributions), 78
tuna.multi_objective.study), 153	distribution_to_json() (in module op-
create_study() (in module optuna.study), 254	tuna.distributions), 84
create_trial() (in module optuna.trial), 280	distributions (optuna.multi_objective.trial.FrozenMultiObjectiveTrial
crossover() (optuna.samplers.nsgaii.BaseCrossover	attribute), 160
method), 211	${\tt distributions} \ (optuna.multi_objective.trial.MultiObjectiveTrial$
${\tt crossover}$ () $(optuna. samplers. nsgaii. BLXAlpha Crossove$	r property), 157
method), 213	distributions (optuna.trial.FrozenTrial property), 277
crossover() (optuna.samplers.nsgaii.SBXCrossover	distributions (optuna.trial.Trial property), 263
method), 215	<pre>dump_best_config() (in module op-</pre>
crossover() (optuna.samplers.nsgaii.SPXCrossover	tuna.integration.allennlp), 92
method), 214	DuplicatedStudyError, 86
crossover() (optuna.samplers.nsgaii.UNDXCrossover	duration (optuna.trial.FrozenTrial property), 277
method), 217	E
crossover() (optuna.samplers.nsgaii.UniformCrossover	
method), 212 crossover() (optuna.samplers.nsgaii.VSBXCrossover	enable_default_handler() (in module op-
method), 216	tuna.logging), 139
method), 210	enable_propagation() (in module optuna.logging),
D	140
datetime_complete (op-	enqueue_trial() (op- tuna.multi_objective.study.MultiObjectiveStudy
tuna.multi_objective.trial.FrozenMultiObjectiveT	· · · · · · · · · · · · · · · · · · ·
attribute), 160	enqueue_trial() (optuna.study.Study method), 247
datetime_complete (optuna.trial.FrozenTrial at-	
tribute), 275	method), 88
**	memoa), 60 t ieฟฮูโซน์เซไ() dloptuna.importance.MeanDecreaseImpurityImportanceEvalu
attribute), 160	method), 90
datetime_start(optuna.multi_objective.trial.MultiObjec	
property), 156	F
datetime_start (optuna.study.StudySummary at-	FAIL (optuna.trial.TrialState attribute), 279
tribute), 261	· • //

<pre>fail_stale_trials() (in module optuna.storages),</pre>	<pre>get_failed_trial_callback() (op- tuna.storages.RedisStorage method), 233</pre>
<pre>fail_stale_trials() (optuna.storages.RDBStorage method), 222</pre>	<pre>get_head_version()</pre>
<pre>fail_stale_trials() (optuna.storages.RedisStorage method), 233</pre>	<pre>get_heartbeat_interval() (op- tuna.storages.RDBStorage method), 223</pre>
FanovaImportanceEvaluator (class in optuna.importance), 88	<pre>get_heartbeat_interval() (op- tuna.storages.RedisStorage method), 234</pre>
FastAIPruningCallback (in module op- tuna.integration), 103	get_n_trials() (optuna.storages.RDBStorage method), 223
FastAIV1PruningCallback (class in optuna.integration), 101	<pre>get_n_trials()</pre>
FastAIV2PruningCallback (class in optuna.integration), 102	<pre>get_param_importances() (in module op- tuna.importance), 87</pre>
file	<pre>get_params() (optuna.integration.OptunaSearchCV</pre>
optuna-study-optimize command line option,71	<pre>method), 129 get_pareto_front_trials() (op-</pre>
fit() (optuna.integration.OptunaSearchCV method), 128	tuna.multi_objective.study.MultiObjectiveStudy method), 151
FixedTrial (class in optuna.trial), 271	<pre>get_study_directions() (op-</pre>
FloatDistribution (class in optuna.distributions), 73	tuna.storages.RDBStorage method), 223
FrozenMultiObjectiveTrial (class in op-	<pre>get_study_directions() (op-</pre>
tuna.multi_objective.trial), 159	tuna.storages.RedisStorage method), 234
FrozenTrial (class in optuna.trial), 274	<pre>get_study_id_from_name() (op-</pre>
, , , , , , , , , , , , , , , , , , , ,	tuna.storages.RDBStorage method), 223
G	<pre>get_study_id_from_name() (op-</pre>
<pre>get_all_study_summaries() (in module optuna), 66</pre>	tuna.storages.RedisStorage method), 234
get_all_study_summaries() (in module op- tuna.study), 259	<pre>get_study_id_from_trial_id() (op- tuna.storages.RDBStorage method), 224</pre>
get_all_study_summaries() (op-	<pre>get_study_id_from_trial_id() (op-</pre>
tuna.storages.RDBStorage method), 222	tuna.storages.RedisStorage method), 234
get_all_study_summaries() (op-	<pre>get_study_name_from_id() (op-</pre>
	tuna.storages.RDBStorage method), 224
tuna.storages.RedisStorage method), 233 get_all_trials() (optuna.storages.RDBStorage	get_study_name_from_id() (op-
- 1	tuna.storages.RedisStorage method), 234
method), 222	get_study_system_attrs() (op-
get_all_trials() (optuna.storages.RedisStorage	tuna.storages.RDBStorage method), 224
method), 233	get_study_system_attrs() (op-
get_all_versions() (optuna.storages.RDBStorage	tuna.storages.RedisStorage method), 235
method), 222	
get_best_booster() (op-	<pre>get_study_user_attrs() (op- tuna.storages.RDBStorage method), 224</pre>
tuna.integration.lightgbm.LightGBMTuner	
method), 107	
get_best_booster() (op-	tuna.storages.RedisStorage method), 235
tuna.integration.lightgbm.LightGBMTunerCV $method$), 110	<pre>get_trial() (optuna.storages.RDBStorage method),</pre>
<pre>get_best_trial()</pre>	<pre>get_trial() (optuna.storages.RedisStorage method),</pre>
<pre>get_best_trial() (optuna.storages.RedisStorage</pre>	<pre>get_trial_id_from_study_id_trial_number()</pre>
method), 233	(optuna.storages.RDBStorage method), 224
<pre>get_current_version() (op-</pre>	<pre>get_trial_id_from_study_id_trial_number()</pre>
tuna.storages.RDBStorage method), 223	(optuna.storages.RedisStorage method), 235
<pre>get_failed_trial_callback() (op-</pre>	<pre>get_trial_number_from_id() (op-</pre>
tuna.storages.RDBStorage method), 223	tuna.storages.RDBStorage method), 225
	<pre>get_trial_number_from_id() (op-</pre>

tuna.storages.RedisStorage method), 235	117
get_trial_param() (optuna.storages.RDBStorage	infer_relative_search_space() (op-
method), 225	tuna.integration.SkoptSampler method),
get_trial_param() (optuna.storages.RedisStorage	132
method), 236	infer_relative_search_space() (op-
<pre>get_trial_params() (optuna.storages.RDBStorage</pre>	tuna.multi_objective.samplers.BaseMultiObjectiveSampler method), 141
<pre>get_trial_params() (optuna.storages.RedisStorage</pre>	<pre>infer_relative_search_space() (op-</pre>
method), 236	$tuna.multi_objective.samplers. MOTPEMultiObjective Sampler$
get_trial_system_attrs() (op-	method), 149
tuna.storages.RDBStorage method), 225	<pre>infer_relative_search_space() (op-</pre>
get_trial_system_attrs() (op-	tuna.multi_objective.samplers.NSGAIIMultiObjectiveSampler
tuna.storages.RedisStorage method), 236	method), 143
get_trial_user_attrs() (op-	<pre>infer_relative_search_space() (op-</pre>
tuna.storages.RDBStorage method), 225	tuna.multi_objective.samplers.RandomMultiObjectiveSampler
get_trial_user_attrs() (op-	method), 146
tuna.storages.RedisStorage method), 236	infer_relative_search_space() (op-
get_trials()(optuna.multi_objective.study.MultiObjecti	
method), 151	infer_relative_search_space() (op-
<pre>get_trials() (optuna.study.Study method), 247 get_verbosity() (in module optuna.logging), 137</pre>	tuna.samplers.CmaEsSampler method), 194
GridSampler (class in optuna.samplers), 180	<pre>infer_relative_search_space() (op-</pre>
	tuna.samplers.GridSampler method), 181
H	<pre>infer_relative_search_space()</pre>
high (optuna.distributions.DiscreteUniformDistribution	tuna.samplers.MOTPESampler method),
attribute), 79	204
high (optuna.distributions.FloatDistribution attribute),	<pre>infer_relative_search_space()</pre>
73	tuna.samplers.NSGAIISampler method),
high (optuna.distributions.IntDistribution attribute), 75	200
high (optuna.distributions.IntLogUniformDistribution	<pre>infer_relative_search_space() (op-</pre>
attribute), 81	tuna. samplers. Partial Fixed Sampler method),
high (optuna.distributions.IntUniformDistribution	196
attribute), 80	<pre>infer_relative_search_space() (op-</pre>
high (optuna.distributions.LogUniformDistribution at-	$tuna. samplers. QMC Sampler\ method), 208$
tribute), 77	<pre>infer_relative_search_space() (op-</pre>
high (optuna.distributions.UniformDistribution at-	tuna.samplers.RandomSampler method),
tribute), 76	184
HyperbandPruner (class in optuna.pruners), 171	<pre>infer_relative_search_space() (op-</pre>
hyperopt_parameters() (op-	tuna.samplers.TPESampler method), 189
tuna.samplers.MOTPESampler static method),	IntDistribution (class in optuna.distributions), 75
203	intermediate_values (op-
hyperopt_parameters() (op-	tuna.multi_objective.trial.FrozenMultiObjectiveTrial
tuna.samplers.TPESampler static method),	attribute), 160
189	intermediate_values (optuna.trial.FrozenTrial attribute), 276
	<pre>intersection_search_space() (in module op-</pre>
<pre>infer_relative_search_space()</pre>	tuna.samplers), 210
tuna.integration.BoTorchSampler method),	<pre>IntersectionSearchSpace (class in optuna.samplers),</pre>
95	209
<pre>infer_relative_search_space() (op-</pre>	IntLogUniformDistribution (class in op-
tuna.integration.CmaEsSampler method),	tuna.distributions), 81
120	IntUniformDistribution (class in op-
<pre>infer_relative_search_space() (op-</pre>	tuna.distributions), 80
tuna.integration.PyCmaSampler method),	inverse_transform (op-

tuna.integration.OptunaSearchCV property),	optuna-study-optimize command line
129 property),	option, 71
is_available() (in module optuna.visualization), 290	MINIMIZE (optuna.study.StudyDirection attribute), 260
is_available() (in module op-	MLflowCallback (class in optuna.integration), 111
tuna.visualization.matplotlib), 307	module
is_heartbeat_enabled() (op-	optuna, 61
· ·	optuna.cli,67
tuna.storages.RDBStorage method), 226	-
is_heartbeat_enabled() (op-	optuna.distributions,73
tuna.storages.RedisStorage method), 236	optuna.exceptions, 84
I	optuna.importance, 86
J	optuna.integration, 90
<pre>json_to_distribution() (in module op-</pre>	optuna.logging, 136
tuna.distributions), 84	optuna.multi_objective, 141
	optuna.multi_objective.samplers,141
ζ	optuna.multi_objective.study,150
KerasPruningCallback (class in optuna.integration),	optuna.multi_objective.trial,155
103	${\tt optuna.multi_objective.visualization}, 160$
	optuna.pruners, 162
<u>_</u>	optuna.samplers,175
Last_step (optuna.trial.FrozenTrial property), 277	optuna.samplers.nsgaii,210
LightGBMPruningCallback (class in op-	optuna.storages, 218
tuna.integration), 104	optuna.study, 242
LightGBMTuner (class in optuna.integration.lightgbm),	optuna.trial,262
105	optuna.visualization,281
	optuna.visualization.matplotlib, 290
in op- tuna.integration.lightgbm), 108	MOTPEMultiObjectiveSampler (class in op-
Load_study() (in module optuna), 63	tuna.multi_objective.samplers), 147
Load_study() (in module optuna.multi_objective.study),	MOTPESampler (class in optuna.samplers), 201
155	MultiObjectiveStudy (class in op-
Load_study() (in module optuna.study), 256	tuna.multi_objective.study), 150
Log (optuna.distributions.FloatDistribution attribute), 73	MultiObjectiveTrial (class in op-
Log (optuna.distributions.IntDistribution attribute), 75	tuna.multi_objective.trial), 156
	MXNetPruningCallback (class in optuna.integration),
LogUniformDistribution (class in optuna.distributions), 77	115
Low (optuna.distributions.DiscreteUniformDistribution	N
attribute), 79	n_objectives(optuna.multi_objective.study.MultiObjectiveStudy
Low (optuna.distributions.FloatDistribution attribute), 73	property), 152
Low (optuna.distributions.IntDistribution attribute), 75	n_parents (optuna.samplers.nsgaii.BaseCrossover
Low (optuna.distributions.IntLogUniformDistribution at-	property), 212
tribute), 81	n_splits_ (optuna.integration.OptunaSearchCV at-
Low (optuna.distributions.IntUniformDistribution at-	tribute), 126
tribute), 80	n_trials (optuna.study.StudySummary attribute), 261
Low (optuna.distributions.LogUniformDistribution	n_trials_ (optuna.integration.OptunaSearchCV prop-
attribute), 77	erty), 129
Low (optuna.distributions.UniformDistribution attribute),	NopPruner (class in optuna.pruners), 165
76	NOT_SET (optuna.study.StudyDirection attribute), 260
M	
· · ·	NSGAIIMultiObjectiveSampler (class in optuna.multi_objective.samplers), 143
MAXIMIZE (optuna.study.StudyDirection attribute), 260	NSGAIISampler (class in optuna.samplers), 198
MaxTrialsCallback (class in optuna.study), 259	
MeanDecreaseImpurityImportanceEvaluator(class	number (optuna.multi_objective.trial.FrozenMultiObjectiveTrial
in optuna.importance), 89	attribute), 159
MedianPruner (class in optuna.pruners), 163	number (optuna.multi_objective.trial.MultiObjectiveTrial
nethod	property), 157

```
number (optuna.trial.FrozenTrial attribute), 275
                                                    optuna.trial
number (optuna.trial.Trial property), 263
                                                        module, 262
                                                    optuna.visualization
\mathbf{O}
                                                        module, 281
\verb"on_epoch"()" (\textit{optuna.integration.AllenNLPPruningCallback"} \texttt{Optuna.visualization.matplotlib} \\
                                                        module, 290
        method), 93
                                                    optuna-ask command line option
optimize()
                 (optuna.integration.ChainerMNStudy
                                                        --direction, 68
        method), 101
{\tt optimize()} \ (optuna.multi\_objective.study. MultiObjectiveStudy \ \hbox{--}directions, 68
                                                        --flatten, 69
        method), 152
                                                        --format, 69
optimize() (optuna.study.Study method), 248
                                                        --sampler, 68
optuna
                                                        --sampler-kwargs, 69
    module, 61
                                                        --search-space, 69
optuna command line option
                                                        --study-name, 68
    --debug, 68
                                                        -f, 69
    --log-file, 68
                                                    optuna-best-trial command line option
    --quiet, 68
                                                        --flatten, 69
    --storage, 68
                                                        --format. 69
    --verbose, 68
                                                        --study-name, 69
    --version, 68
                                                        -f. 69
    -q, 68
                                                    optuna-best-trials command line option
    -v, 68
                                                        --flatten, 69
optuna.cli
                                                        --format. 69
    module, 67
                                                        --study-name, 69
optuna.distributions
                                                        -f. 69
    module, 73
                                                    optuna-create-study command line option
optuna.exceptions
                                                        --direction, 70
    module, 84
                                                        --directions, 70
optuna.importance
                                                        --skip-if-exists, 70
    module, 86
                                                        --study-name, 70
optuna.integration
                                                    optuna-delete-study command line option
    module, 90
                                                        --study-name, 70
optuna.logging
                                                    optuna-studies command line option
    module, 136
                                                        --flatten, 70
optuna.multi_objective
                                                        --format, 70
    module, 141
                                                        -f.70
optuna.multi_objective.samplers
                                                    optuna-study-optimize command line option
    module, 141
                                                        --n-jobs, 71
optuna.multi_objective.study
                                                        --n-trials, 71
    module, 150
                                                        --study, 71
optuna.multi_objective.trial
                                                        --study-name, 71
    module, 155
                                                        --timeout. 71
optuna.multi_objective.visualization
                                                        file, 71
    module, 160
                                                        method, 71
optuna.pruners
                                                    optuna-study-set-user-attr command line
    module, 162
                                                            option
optuna.samplers
                                                        --key, 72
    module, 175
                                                        --study, 71
optuna.samplers.nsgaii
                                                        --study-name, 71
    module, 210
                                                        --value, 72
optuna.storages
                                                        -k, 72
    module, 218
                                                        -v. 72
optuna.study
                                                    optuna-tell command line option
    module, 242
```

skip-if-finished,72	<pre>predict (optuna.integration.OptunaSearchCV prop-</pre>
state, 72	erty), 129
study-name, 72	predict_log_proba (op-
trial-number,72	tuna.integration.OptunaSearchCV property),
values, 72	129
optuna-trials command line option	predict_proba (optuna.integration.OptunaSearchCV
flatten, 72	property), 129
format, 72	prune() (optuna.pruners.BasePruner method), 162
study-name, 72 -f, 72	prune() (optuna.pruners.HyperbandPruner method), 173
OptunaError, 85	prune() (optuna.pruners.MedianPruner method), 164
OptunaSearchCV (class in optuna.integration), 125	prune() (optuna.pruners.NopPruner method), 165
	prune() (optuna.pruners.PatientPruner method), 167
P	prune() (optuna.pruners.PercentilePruner method), 169
params(optuna.multi_objective.trial.FrozenMultiObjective	
attribute), 160	method), 171
params (optuna.multi_objective.trial.MultiObjectiveTrial	prune() (optuna.pruners.ThresholdPruner method), 175
property), 157	PRUNED (optuna.trial.TrialState attribute), 279
params (optuna.trial.FrozenTrial attribute), 275	PyCmaSampler (class in optuna.integration), 115
params (optuna.trial.Trial property), 263	PyTorchIgnitePruningHandler (class in op-
PartialFixedSampler (class in optuna.samplers), 195	tuna.integration), 121
PatientPruner (class in optuna.pruners), 166	PyTorchLightningPruningCallback (class in op-
PercentilePruner (class in optuna.pruners), 167	tuna.integration), 122
plot_contour() (in module optuna.visualization), 282	Q
plot_contour() (in module op-	
tuna.visualization.matplotlib), 291	q (optuna.distributions.DiscreteUniformDistribution
plot_edf() (in module optuna.visualization), 283	property), 79
plot_edf() (in module optuna.visualization.matplotlib), 293	qehvi_candidates_func() (in module optuna.integration.botorch), 97
plot_intermediate_values() (in module op-	<pre>qei_candidates_func() (in module op-</pre>
tuna.visualization), 284	tuna.integration.botorch), 97
plot_intermediate_values() (in module op-	QMCSampler (class in optuna.samplers), 205
tuna.visualization.matplotlib), 295	<pre>qparego_candidates_func() (in module op-</pre>
plot_optimization_history() (in module op-	tuna.integration.botorch), 98
tuna.visualization), 285	D
plot_optimization_history() (in module op-	R
tuna.visualization.matplotlib), 297	RandomMultiObjectiveSampler (class in op-
plot_parallel_coordinate() (in module op-	tuna.multi_objective.samplers), 145
tuna.visualization), 286 plot_parallel_coordinate() (in module op-	RandomSampler (class in optuna.samplers), 183
plot_parallel_coordinate() (in module op- tuna.visualization.matplotlib), 299	RDBStorage (class in optuna.storages), 218
plot_param_importances() (in module op-	read_trials_from_remote_storage() (op-
tuna.visualization), 287	<pre>tuna.storages.RDBStorage method), 226 read_trials_from_remote_storage() (op-</pre>
plot_param_importances() (in module op-	tuna.storages.RedisStorage method), 236
tuna.visualization.matplotlib), 301	record_heartbeat() (optuna.storages.RDBStorage
plot_pareto_front() (in module op-	method), 226
tuna.multi_objective.visualization), 161	record_heartbeat() (optuna.storages.RedisStorage
plot_pareto_front() (in module op-	method), 237
tuna.visualization), 288	RedisStorage (class in optuna.storages), 229
plot_pareto_front() (in module op-	refit_time_ (optuna.integration.OptunaSearchCV at-
tuna.visualization.matplotlib), 303	tribute), 126
plot_slice() (in module optuna.visualization), 289	$\verb"register()" (optuna. integration. Allen NLPP runing Callback") \\$
plot_slice() (in module op-	class method), 93
tuna.visualization.matplotlib), 305	

remove_session method		storages.RDBStorage	run()	(optuna.integration.lightgbm.LightGE method), 110	3MTunerCV	
remove_session method		torages.RedisStorage	RUNNIN	IG (optuna.trial.TrialState attribute), 2'	79	
report()(optu	ıa.multi_objective.tı	rial.MultiObjectiveTric	$_{il}S$			
method	l), 157			e_independent()	(op-	
_	na.trial.FrozenTrial		_	tuna.integration.BoTorchSampler	method),	
_	na.trial.Trial method			96		
reseed_rng()		tion.BoTorchSampler	sample	e_independent()	(op-	
<pre>method reseed_rng()</pre>	* *	ation.CmaEsSampler		tuna.integration.CmaEsSampler 120	method),	
method	<i>l</i>), 120		sample	e_independent()	(op-	
reseed_rng() method		ation.PyCmaSampler		tuna.integration.PyCmaSampler 118	method),	
reseed_rng()	(optuna.integ	gration.SkoptSampler	sample	e_independent()	(op-	
method			_	tuna.integration.SkoptSampler	method),	
method	l), 142	tive.samplers.BaseMu	samnle	iveSampler	(on-	
reseed_rng()	optuna.multi_objec	tive.samplers.MOTPE	MultiObj	iectiveg:multerobjective.samplers.Base.	MultiObiectiveS	Sampler
method	<i>t</i>), 149			method), 142		in a pro-
reseed_rng()	optuna.multi_objec	tive.samplers.NSGAII	MyltiRhi	e <u>clindspenk</u> ent ()	(op-	
method	<i>l</i>), 144		_	tuna.multi objective.samplers.MOT	PEMultiObject	iveSampler
		tive.samplers.Random	MultiObj	iectivesample49	•	•
method			sample	e_independent()	(op-	
	(optuna.samplers.B	aseSampler method),		tuna.multi_objective.samplers.NSG	AIIMultiObjecti	veSampler
178	,			method), 144		
reseed_rng()		plers.CmaEsSampler	sample	e_independent()	(op-	
method		:1C 1 .1 1)		tuna.multi_objective.samplers.Rand	omMultiObject	iveSampler
	(optuna.samplers.G	ridSampler method),		method), 146		
182	(+	1 MOTDEC1	sample	e_independent()	(op-	
reseed_rng()		lers.MOTPESampler	_	tuna.samplers.BaseSampler method		
<pre>method reseed_rng()</pre>	* *	olers.NSGAIISampler	sample	e_independent()	(op-	
method	d), 200	•		tuna.samplers.CmaEsSampler 194	method),	
reseed_rng()		PartialFixedSampler	sample	e_independent()	(op-	
method		MCC 1 1 1		tuna.samplers.GridSampler method		
	optuna.sampters.Q	MCSampler method),	sample	e_independent()	(op-	
208	(amtuu a a auum	long Dan dom Camplen		tuna.samplers.MOTPESampler	method),	
reseed_rng() method		lers.RandomSampler	_	204	,	
	* *	PESampler method),	sample	e_independent()	(op-	
190		-		tuna.samplers.NSGAIISampler 200	method),	
retried_trial		(op-	sample	e_independent()	(op-	
method				tuna.samplers.PartialFixedSampler 197	method),	
retry_history		(op-	sample	e_independent()	(op-	
	orages.RetryFailedT	FrialCallback static		tuna.samplers.QMCSampler method	d), 208	
method			sample	e_independent()	(op-	
RetryFailedTi		(class in op-		tuna. samplers. Random Sampler	method),	
	orages), 240	DE		185		
92		PExecutor method),	sample	e_independent() (optuna.samplers.T method), 190	PESampler	
_		gbm.LightGBMTuner	sample	_indices_	(op-	
method	d), 107		-	tuna.integration.OptunaSearchCV	attribute),	

127	${\tt score_samples}$ (optuna.integration.OptunaSearchCV
<pre>sample_relative()</pre>	property), 130
tuna.integration.BoTorchSampler method),	scorer_ (optuna.integration.OptunaSearchCV at-
96	tribute), 127
<pre>sample_relative() (op-</pre>	set_params() (optuna.integration.OptunaSearchCV
tuna.integration.CmaEsSampler method),	method), 130
121	set_study_directions() (op-
<pre>sample_relative()</pre>	tuna.storages.RDBStorage method), 226
tuna.integration.PyCmaSampler method),	set_study_directions() (op-
118	tuna.storages.RedisStorage method), 237
sample_relative() (optuna.integration.SkoptSampler	set_study_system_attr() (op-
<pre>method), 133 sample_relative() (op-</pre>	<pre>tuna.storages.RDBStorage method), 226 set_study_system_attr() (op-</pre>
	set_study_system_attr() (op- veSampler tuna.storages.RedisStorage method), 237
method), 142	set_study_user_attr() (op-
sample_relative() (op-	tuna.storages.RDBStorage method), 227
tuna.multi_objective.samplers.MOTPEMultiObje	
method), 150	tuna.storages.RedisStorage method), 237
sample_relative() (op-	set_system_attr() (op-
	ctiveSampleuna.multi_objective.study.MultiObjectiveStudy
method), 144	method), 153
<pre>sample_relative() (op-</pre>	
	ectiveSamplama.multi_objective.trial.MultiObjectiveTrial
method), 147	method), 157
<pre>sample_relative() (optuna.samplers.BaseSampler</pre>	<pre>set_system_attr() (optuna.study.Study method), 250</pre>
method), 179	<pre>set_system_attr() (optuna.trial.Trial method), 264</pre>
<pre>sample_relative() (optuna.samplers.CmaEsSampler</pre>	<pre>set_trial_intermediate_value() (op-</pre>
method), 195	tuna.storages.RDBStorage method), 227
<pre>sample_relative() (optuna.samplers.GridSampler</pre>	set_trial_intermediate_value() (op-
method), 182	tuna.storages.RedisStorage method), 238
<pre>sample_relative() (optuna.samplers.MOTPESampler</pre>	<pre>set_trial_param() (optuna.storages.RDBStorage</pre>
method), 205	method), 227
<pre>sample_relative() (optuna.samplers.NSGAIISampler</pre>	set_trial_param() (optuna.storages.RedisStorage
method), 201	method), 238
<pre>sample_relative()</pre>	set_trial_state() (optuna.storages.RDBStorage
tuna.samplers.PartialFixedSampler method),	method), 227
197	set_trial_state() (optuna.storages.RedisStorage
sample_relative() (optuna.samplers.QMCSampler	method), 238
method), 209	set_trial_state_values() (op-
<pre>sample_relative() (optuna.samplers.RandomSampler method), 185</pre>	tuna.storages.RDBStorage method), 228 set_trial_state_values() (op-
sample_relative() (optuna.samplers.TPESampler	set_trial_state_values() (op- tuna.storages.RedisStorage method), 238
method), 190	
sample_train_set() (op-	set_trial_system_attr() (op- tuna.storages.RDBStorage method), 228
tuna.integration.lightgbm.LightGBMTuner	set_trial_system_attr() (op-
method), 107	tuna.storages.RedisStorage method), 239
<pre>sample_train_set() (op-</pre>	set_trial_user_attr() (op-
tuna.integration.lightgbm.LightGBMTunerCV	tuna.storages.RDBStorage method), 228
method), 110	set_trial_user_attr() (op-
sampler(optuna.multi_objective.study.MultiObjectiveStud	· ·
property), 153	set_trial_values() (optuna.storages.RDBStorage
SBXCrossover (class in optuna.samplers.nsgaii), 215	method), 229
<pre>score() (optuna.integration.OptunaSearchCV method),</pre>	<pre>set_trial_values() (optuna.storages.RedisStorage</pre>
129	method), 239

<pre>set_user_attr (optuna.integration.OptunaSearchCV</pre>	tuna.multi_objective.trial.MultiObjectiveTrial method), 158
set_user_attr() (op-	suggest_categorical() (optuna.trial.Trial method),
tuna.multi_objective.study.MultiObjectiveStudy	266
method), 153	<pre>suggest_discrete_uniform() (op-</pre>
set_user_attr() (op-	tuna.integration.TorchDistributedTrial
tuna.multi_objective.trial.MultiObjectiveTrial	method), 124
method), 157	suggest_discrete_uniform() (op-
set_user_attr() (optuna.study.Study method), 250	tuna.multi_objective.trial.MultiObjectiveTrial
set_user_attr() (optuna.trial.Trial method), 265	method), 158
set_verbosity() (in module optuna.logging), 138	suggest_discrete_uniform() (op-
should_prune() (optuna.trial.FrozenTrial method), 277	tuna.trial.FixedTrial method), 273
should_prune() (optuna.trial.Trial method), 266	suggest_discrete_uniform() (op-
single() (optuna.distributions.CategoricalDistribution	tuna.trial.FrozenTrial method), 278
method), 83	suggest_discrete_uniform() (optuna.trial.Trial
single() (optuna.distributions.DiscreteUniformDistributi method), 79	
single() (optuna.distributions.FloatDistribution	tuna.multi_objective.trial.MultiObjectiveTrial
method), 74	method), 158
single() (optuna.distributions.IntDistribution method),	suggest_float() (optuna.trial.Trial method), 267
75	suggest_int() (optuna.multi_objective.trial.MultiObjectiveTrial
single() (optuna.distributions.IntLogUniformDistribution	
method), 82	suggest_int() (optuna.trial.Trial method), 269
single() (optuna.distributions.IntUniformDistribution	<pre>suggest_loguniform() (op-</pre>
method), 81	tuna.integration.TorchDistributedTrial
single() (optuna.distributions.LogUniformDistribution	method), 124
method), 78	<pre>suggest_loguniform() (op-</pre>
single() (optuna.distributions.UniformDistribution	tuna.multi_objective.trial.MultiObjectiveTrial
method), 77	method), 159
SkoptSampler (class in optuna.integration), 130	<pre>suggest_loguniform() (optuna.trial.FixedTrial</pre>
SkorchPruningCallback (class in optuna.integration),	method), 273
134	<pre>suggest_loguniform() (optuna.trial.FrozenTrial</pre>
SPXCrossover (class in optuna.samplers.nsgaii), 214	method), 278
$\verb+state+ (optuna.multi_objective.trial.FrozenMultiObjective Trial.FrozenMultiObjective Trial.FrozenM$	Triadggest_loguniform() (optuna.trial.Trial method),
attribute), 159	270
state (optuna.trial.FrozenTrial attribute), 275	<pre>suggest_uniform()</pre>
${\tt step} \ \ (optuna. distributions. Float Distribution \ \ attribute),$	tuna.integration. Torch Distributed Trial
73	method), 124
step (optuna.distributions.IntDistribution attribute), 75	<pre>suggest_uniform()</pre>
${\tt step} (optuna. distributions. Int Log Uniform Distribution$	$tuna.multi_objective.trial.MultiObjectiveTrial$
attribute), 81	method), 159
step (optuna.distributions.IntUniformDistribution	<pre>suggest_uniform() (optuna.trial.FixedTrial method),</pre>
attribute), 80	273
stop() (optuna.study.Study method), 251	<pre>suggest_uniform() (optuna.trial.FrozenTrial method),</pre>
StorageInternalError, 86	278
Study (class in optuna.study), 242	<pre>suggest_uniform() (optuna.trial.Trial method), 271</pre>
<pre>study_ (optuna.integration.OptunaSearchCV attribute),</pre>	system_attrs(optuna.multi_objective.study.MultiObjectiveStudy
127	property), 153
study_name (optuna.study.StudySummary attribute), 261	system_attrs(optuna.multi_objective.trial.MultiObjectiveTrial
StudyDirection (class in optuna.study), 260	property), 159
StudySummary (class in optuna.study), 261	system_attrs (optuna.study.Study property), 251
SuccessiveHalvingPruner (class in optuna.pruners),	system_attrs (optuna.study.StudySummary attribute),
169	261
<pre>suggest_categorical() (op-</pre>	system_attrs (optuna.trial.Trial property), 271

T	to_internal_repr() (op-
tell() (optuna.study.Study method), 251	$tuna. distributions. {\it Uniform Distribution}$
TensorBoardCallback (class in optuna.integration),	method), 77
135	TorchDistributedTrial (class in optuna.integration),
TensorFlowPruningHook (class in optuna.integration),	122
135	TPESampler (class in optuna.samplers), 186
TFKerasPruningCallback (class in op-	track_in_mlflow() (op-
tuna.integration), 136	tuna.integration.MLflowCallback method),
ThresholdPruner (class in optuna.pruners), 174	113
to_external_repr() (op-	train() (in module optuna.integration.lightgbm), 104
tuna. distributions. Categorical Distribution	transform (optuna.integration.OptunaSearchCV prop-
method), 83	erty), 130
to_external_repr() (op-	Trial (class in optuna.trial), 262
tuna. distributions. Discrete Uniform Distribution	TrialPruned, 67, 85
method), 79	trials(optuna.multi_objective.study.MultiObjectiveStudy
to_external_repr() (op-	property), 153
tuna.distributions.FloatDistribution method),	trials (optuna.study.Study property), 253
74	trials_ (optuna.integration.OptunaSearchCV prop- erty), 130
to_external_repr() (op-	• •
tuna.distributions.IntDistribution method),	trials_dataframe (op- tuna.integration.OptunaSearchCV property),
75	130
to_external_repr() (op-	trials_dataframe() (optuna.study.Study method), 253
tuna.distributions.IntLogUniformDistribution	TrialState (class in optuna.trial), 279
method), 82	Titalscate (class in optimalities), 217
to_external_repr() (op-	U
tuna.distributions.IntUniformDistribution	UNDXCrossover (class in optuna.samplers.nsgaii), 217
method), 81	UniformCrossover (class in optuna.samplers.nsgaii),
to_external_repr() (op-	212
tuna. distributions. $LogUniformDistribution$ $method), 78$	UniformDistribution (class in optuna.distributions),
to_external_repr() (op-	76
tuna.distributions.UniformDistribution	upgrade() (optuna.storages.RDBStorage method), 229
method), 77	user_attrs(optuna.multi_objective.study.MultiObjectiveStudy
to_internal_repr() (op-	property), 153
tuna.distributions.CategoricalDistribution	user_attrs(optuna.multi_objective.trial.FrozenMultiObjectiveTrial
method), 83	attribute), 160
to_internal_repr() (op-	user_attrs(optuna.multi_objective.trial.MultiObjectiveTrial
tuna.distributions.DiscreteUniformDistribution	property), 159
method), 80	user_attrs (optuna.study.Study property), 254
to_internal_repr() (op-	user_attrs(optuna.study.StudySummary attribute), 261
tuna.distributions.FloatDistribution method),	user_attrs (optuna.trial.FrozenTrial attribute), 275
74	user_attrs (optuna.trial.Trial property), 271
to_internal_repr() (op-	user_attrs_ (optuna.integration.OptunaSearchCV
tuna.distributions.IntDistribution method),	property), 130
76	M
to_internal_repr() (op-	V
tuna.distributions.IntLogUniformDistribution	value (optuna.trial.FrozenTrial attribute), 275
method), 82	$values ({\it optuna.multi_objective.trial.FrozenMultiObjectiveTrial}$
to_internal_repr() (op-	attribute), 159
tuna. distributions. Int Uniform Distribution	values (optuna.trial.FrozenTrial attribute), 275
method), 81	VSBXCrossover (class in optuna.samplers.nsgaii), 216
to_internal_repr() (op-	10/
$tuna. distributions. Log {\it Uniform Distribution}$	W
method), 78	WAITING (optuna.trial.TrialState attribute), 279

WeightsAndBiasesCallback (class in optuna.integration), 113

Χ

XGBoostPruningCallback (class in optuna.integration), 136